



ZENworks 2020 Asset Inventory Reference

October 2019

Legal Notice

For information about legal notices, trademarks, disclaimers, warranties, export and other use restrictions, U.S. Government rights, patent policy, and FIPS compliance, see <https://www.microfocus.com/about/legal/>.

Copyright © 2008 - 2020 Micro Focus Software Inc. All rights reserved.

The only warranties for products and services of Micro Focus and its affiliates and licensors ("Micro Focus") are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Micro Focus shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

Contents

About This Guide	7
1 Overview	9
1.1 Scanning for Hardware Information	9
1.2 Scanning for Software Information	9
1.3 Scanning for Demographic Information	9
1.4 Security Considerations	10
2 Scanning Managed Devices	11
2.1 Configuring an Inventory Scan	11
2.1.1 Configuring a Scan for the Management Zone	11
2.1.2 Configuring a Scan for Devices in a Folder	14
2.1.3 Configuring an Inventory Scan for a Device	14
2.2 Scheduling an Inventory Scan	15
2.2.1 Configuring an Inventory Scan Schedule for the Management Zone	15
2.2.2 Configuring an Inventory Scan Schedule for Devices in a Folder	17
2.2.3 Configuring an Inventory Scan Schedule for a Device	18
2.3 Running an Inventory Scan	18
2.4 Adding Hardware Products from ZENworks Control Center	19
2.5 Viewing an Inventory Report for a Managed Device	20
2.5.1 Using ZENworks Control Center to View a Managed Device's Inventory	20
2.5.2 Using the ZENworks Icon Menu to View a Managed Device's Inventory	20
2.6 Editing a Managed Device's Inventory Data	21
3 Scanning Inventory Only Devices	23
3.1 Configuring an Inventory Only Scan	23
3.2 Scheduling an Inventory Only Scan	25
3.2.1 To Configure an Inventory Only Scan Schedule	25
3.3 Viewing an Inventory Report for an Inventory Only Device	27
3.4 Editing the Demographic Data of an Inventory Only Device	27
3.5 Enabling Reconciliation	28
3.6 Using the Portable Collector	28
3.6.1 Running the Portable Collector on a Windows Device	29
3.6.2 Running the Portable Collector on an OS X Device	29
3.6.3 Running the Portable Collector on a Linux Device	29
3.6.4 Importing Data Gathered with the Portable Collector	30
4 Scanning Demographic Data	31
4.1 Configuring the Collection Data Form	31
4.1.1 Configuring the Collection Data Form for the Management Zone	32
4.1.2 Configuring the Collection Data Form for Devices in a Folder	33
4.1.3 Configuring the Collection Data Form for a Device	33
4.2 Deploying the Collection Data Form	34

4.3	Configuring the Collection Data Form Launch Schedule	34
4.3.1	Configuring the Collection Data Form Launch Schedule for the Management Zone	34
4.3.2	Scheduling the Deployment of the Collection Data Form for Devices in a Folder	37
4.3.3	Scheduling the Deployment of the Collection Data Form for a Device	37
4.4	Launching the Collection Data Form Using a Quick Task	38
4.5	Deploying the Data Collection Form Using a Device Task	38
4.6	Scanning Demographic Data on an Inventory Only Device	38
5	Importing Demographic Data	41
5.1	Creating LDAP Import Tasks	41
5.2	Executing LDAP Import Tasks	48
5.3	Viewing or Editing LDAP Import Tasks	48
6	Creating Local Software Products	49
6.1	Understanding Local Software Products	49
6.2	Understanding the Local Software Products Panel	49
6.3	Creating Local Software Products	50
6.4	Consolidating Local Software Products	50
6.5	Editing Product Information	51
6.5.1	Editing the Product Naming Data	51
6.5.2	Editing the Product Recognition Data	52
6.6	Updating the ZENworks Knowledgebase	53
6.6.1	Merging Local Software Products with the ZENworks Knowledgebase	53
6.6.2	Updating the ZENworks Knowledgebase with the PRU	53
6.7	Creating a New Software Fingerprint Request	54
6.7.1	Working with the SWID Wizard	54
7	Using Administrator-Defined Fields	57
7.1	About Administrator-Defined Fields	57
7.2	Creating an Administrator-Defined Field	57
7.3	Removing Administrator-Defined Fields from Web Console Reports	59
8	Using Reports	61
8.1	Using Inventory Standard Reports	61
8.1.1	Available Standard Reports	61
8.1.2	Running a Standard Report	63
8.2	Using Inventory Custom Reports	64
8.2.1	Available Custom Reports	64
8.2.2	Running a Custom Report	65
8.2.3	Creating a Custom Report	66
8.2.4	Scheduling a Custom Report and Sending Notifications	67
8.2.5	Configuring E-mail Addresses	67
8.2.6	Editing a Custom Report	68
8.2.7	Moving a Custom Report	69
8.2.8	Deleting a Custom Report or Folder	69
8.2.9	Viewing Scheduled Reports by Date and Title	70
8.2.10	Importing New Report Definitions	70
8.3	Inventory Report Rights	70

8.4	Administrator Rights	71
8.5	Manually Adding New Device Manufacturer or Model to the Inventory Reports	71
8.5.1	To add a new model to an existing manufacturer	72
8.5.2	To add a new manufacturer and model	72
8.6	Running Scheduled Report	72
9	Managing Component Data	75
9.1	Searching for a Component and Viewing Component Data	75
9.2	Editing the Component Data	76
9.2.1	Using Administrator-Defined Fields	76
10	Managing Product Data	77
10.1	Searching for a Product and Viewing Product Data	77
10.2	Reclassifying a Product	78
10.3	Managing Product Categories and Subcategories	78
10.3.1	Creating a New Product Category	78
10.3.2	Renaming a Product Category	79
10.3.3	Deleting a Product Category	79
10.3.4	Creating a New Product Subcategory	79
10.3.5	Renaming a Product Subcategory	79
10.3.6	Deleting a Product Subcategory	80
11	Purge Inventory History	81
11.1	Configuring Inventory History Purge Settings for the Zone	81
11.2	Overriding Inventory History Purge Settings at the Device Level	82
A	Inventory Workflow	85
A.1	Inventory Workflow on a Workstation	85
A.2	Inventory Workflow on a Primary Server	85
A.3	Inventory Workflow on an Inventory Only Device	86
A.4	Troubleshooting the Inventory Workflow	86
B	Troubleshooting Asset Inventory	87

About This Guide

This *ZENworks Asset Inventory Reference* includes information to help you successfully perform inventory tasks. The information in this guide is organized as follows:

- ♦ [Chapter 1, “Overview,” on page 9](#)
- ♦ [Chapter 2, “Scanning Managed Devices,” on page 11](#)
- ♦ [Chapter 3, “Scanning Inventory Only Devices,” on page 23](#)
- ♦ [Chapter 4, “Scanning Demographic Data,” on page 31](#)
- ♦ [Chapter 5, “Importing Demographic Data,” on page 41](#)
- ♦ [Chapter 6, “Creating Local Software Products,” on page 49](#)
- ♦ [Chapter 7, “Using Administrator-Defined Fields,” on page 57](#)
- ♦ [Chapter 8, “Using Reports,” on page 61](#)
- ♦ [Chapter 9, “Managing Component Data,” on page 75](#)
- ♦ [Chapter 10, “Managing Product Data,” on page 77](#)
- ♦ [Chapter 11, “Purge Inventory History,” on page 81](#)
- ♦ [Appendix A, “Inventory Workflow,” on page 85](#)
- ♦ [Appendix B, “Troubleshooting Asset Inventory,” on page 87](#)

Audience

This guide is intended for ZENworks administrators.

Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation.

Additional Documentation

ZENworks with Asset Inventory is supported by other documentation (in both PDF and HTML formats) that you can use to learn about and implement the product. For additional documentation, see the [ZENworks documentation Web site](#).

1 Overview

ZENworks Asset Inventory allows you to take an inventory of all the devices in your Management Zone, including data on hardware, software, and demographics.

The following sections contain additional information:

- ♦ [Section 1.1, “Scanning for Hardware Information,” on page 9](#)
- ♦ [Section 1.2, “Scanning for Software Information,” on page 9](#)
- ♦ [Section 1.3, “Scanning for Demographic Information,” on page 9](#)
- ♦ [Section 1.4, “Security Considerations,” on page 10](#)

1.1 Scanning for Hardware Information

Asset Inventory allows you to scan and collect hardware data for all the devices in your Management Zone. The hardware data includes information about keyboard, video adapter, bus adapter, monitor, CD/DVD, LAN adapter, diskette, hard drive, memory module, parallel port, printer, mouse, BIOS, serial port, system board, processor, USB keyboard and USB port. You might also find other categories of hardware components apart from the ones listed. The unrecognized hardware components are listed as Other Hardware in the inventory scan report. You can view the collected hardware data in several ways by using standard and custom reports.

NOTE

On a SLES or SLED Inventory Only device, for the inventory scan to work correctly, prior to running the scan, you need to ensure that the `lsb-release` rpm is installed.

1.2 Scanning for Software Information

Asset Inventory allows you to scan all the devices in your Management Zone and collect data on what software products are installed on those devices. Asset Inventory can identify thousands of products and allows you to define additional products so that they can be recognized on subsequent scans and on other devices. It also allows you to collect data on how many virtual machines are present on the device. Data can be displayed through a variety of reports. This data can be used for general information, license compliance, and so on.

1.3 Scanning for Demographic Information

Asset Inventory allows you to collect demographic information by using one of the following:

- ♦ **Collection Data Form:** You can poll workstation users for demographic data, such as name, phone number, department, cost center, and so on. This information is added to the inventory data, giving you a complete picture of all the devices in your Management Zone.

- ♦ **LDAP Import Tasks:** You can import demographic data from Microsoft Active Directory and Novell eDirectory to the Novell ZENworks database. You can set up tasks for different Active Directory or e-Directory LDAP sources, and schedule each task individually.

1.4 Security Considerations

No integrity protection is provided for inventory data because it is collected from agents. Because access to inventory data could provide information on how to attack a machine in the Management Zone, Asset Inventory should only be used in a secure environment. In addition, the database where the inventory data is stored should also be protected.

To avoid security threats, Windows managed devices have restricted permissions when accessing network drives for the processes which run in System context. The ZENworks Agent can detect Network drives only with administrator privilege access.

2 Scanning Managed Devices

An inventory scan of your managed devices provides you with a detailed report of each device's hardware, software, and demographic data. The following sections provide information on inventory scans:

- ♦ [Section 2.1, “Configuring an Inventory Scan,” on page 11](#)
- ♦ [Section 2.2, “Scheduling an Inventory Scan,” on page 15](#)
- ♦ [Section 2.3, “Running an Inventory Scan,” on page 18](#)
- ♦ [Section 2.4, “Adding Hardware Products from ZENworks Control Center,” on page 19](#)
- ♦ [Section 2.5, “Viewing an Inventory Report for a Managed Device,” on page 20](#)
- ♦ [Section 2.6, “Editing a Managed Device’s Inventory Data,” on page 21](#)

2.1 Configuring an Inventory Scan

An inventory scan allows you to collect data from managed devices in your Management Zone. By default, the inventory settings are preconfigured.

You can define the scan settings at three levels:

- ♦ **Management Zone:** The settings are inherited by all device folders and devices. To configure a scan for the management zone, see [Section 2.1.1, “Configuring a Scan for the Management Zone,” on page 11](#).
- ♦ **Device Folder:** The settings are inherited by all devices contained within the folder or its subfolders. Overrides the Management Zone settings. To configure a scan for the devices in a folder, see [Section 2.1.2, “Configuring a Scan for Devices in a Folder,” on page 14](#).
- ♦ **Device:** The settings apply only to the device for which they are configured. Overrides the settings at the Management Zone level and the device folder level. To configure a scan for a device, see [Section 2.1.3, “Configuring an Inventory Scan for a Device,” on page 14](#).

2.1.1 Configuring a Scan for the Management Zone

- 1 In ZENworks Control Center, click **Configuration**, then in the Management Zone Settings panel, click **Inventory**.
- 2 Click **Inventory** in the category list.
- 3 In the Scan Now panel, configure how to run an on-demand inventory scan by using a Quick Task, device task, or by using the ZENworks Icon menu.

For more information on running an on-demand inventory scan, see [Section 2.3, “Running an Inventory Scan,” on page 18](#).

Collect Software Applications: Select this option if you want to scan for software applications. This setting is selected by default.

Collect Software File Information: Select this option if you want to scan for software file information that can be used to identify software products that aren't recognized by the ZENworks Knowledgebase. If you plan to create Local Software Products and add them to the knowledgebase, this option must be selected. For more information, see [Chapter 6, "Creating Local Software Products,"](#) on page 49.

Collect Hardware: Select this option if you want to scan for hardware data. This setting is selected by default.

Launch Collection Data Form: Select this option if you want to send out the Collection Data Form, which is used to collect demographic data. For more information, see [Chapter 4, "Scanning Demographic Data,"](#) on page 31.

Run DMTF Translator: Select this option if you want to run the DMTF (Desktop Management Task Force) Translator. The DMTF translator converts the inventory data to formats that can be used by other tools and puts it on the local machine.

User Can Initiate Scan: Select this option if you want to allow the workstation user to initiate a scan by using the ZENworks Icon.

Collect MSI Information: Select this option if you want to scan for information about the installed Microsoft Installer (MSI) files that are used for installation, storage, and removal of programs on a device.

- 4 In the **First Scan** panel, configure how you want to run an initial inventory scan on a device.

Collect Software Applications: Select this option if you want to scan for software applications. This setting is selected by default.

Collect Software File Information: Select this option if you want to scan for software file information that can be used to identify software products that aren't recognized by the ZENworks Knowledgebase. If you plan to create Local Software Products and add them to the knowledgebase, this option must be selected. For more information, see [Chapter 6, "Creating Local Software Products,"](#) on page 49.

Collect Hardware: Select this option if you want to scan for hardware data. This setting is selected by default.

Launch Collection Data Form: Select this option if you want to send out the Collection Data Form, which is used to collect demographic data, when a scan is initiated. For more information, see [Chapter 4, "Scanning Demographic Data,"](#) on page 31.

Run DMTF Translator: Select this option if you want to run the DMTF (Desktop Management Task Force) Translator. The DMTF translator converts the inventory data to formats that can be used by other tools and puts it on the local machine.

Collect MSI Information: Select this option if you want to scan for information about the installed Microsoft Installer (MSI) files that are used for installation, storage, and removal of programs on a device.

- 5 In the **Recurring Scan** panel, configure how you want to run scans based on a schedule.

Collect Software Applications: Select this option if you want to scan for software applications. This setting is selected by default.

Collect Software File Information: Select this option if you want to scan for software file information that can be used to identify software products that aren't recognized by the ZENworks Knowledgebase. If you plan to create Local Software Products and add them to the knowledgebase, this option must be selected. For more information, see [Chapter 6, "Creating Local Software Products,"](#) on page 49.

Collect Hardware: Select this option if you want to scan for hardware data. This setting is selected by default.

Launch Collection Data Form: Select this option if you want to send out the Collection Data Form, which is used to collect demographic data. For more information, see [Chapter 4, “Scanning Demographic Data,”](#) on page 31.

Run DMTF Translator: Select this option if you want to run the DMTF (Desktop Management Task Force) Translator. The DMTF translator converts the inventory data to formats that can be used by other tools and puts it on the local machine.

Collect MSI Information: Select this option if you want to scan for information about the installed Microsoft Installer (MSI) files that are used for installation, storage, and removal of programs on a device.

6 In the Software Applications panel, configure which directories to skip.

Skipping directories is useful in limiting the scope of the scan. Any entry added to the list skips that directory and all the subdirectories below it.

- ♦ To add a directory, specify a directory in the **Skip Directories** field, then click **Add**.
- ♦ To edit an existing directory, select the directory, click **Edit**, edit the directory, then click **OK**.
- ♦ To delete an existing directory, select the directory, then click **Remove**.

7 In the Software Files panel, configure which types of files to scan for.

Software applications discovered in an inventory scan are identified by specific files associated with the product. These identifications are kept in the ZENworks Knowledgebase. To identify products that aren't in the knowledgebase, you can search for files that are associated with an unrecognized product and use the file information to create a new product identification called a Local Software Product. This Local Software Product information can then be merged with the knowledgebase so that these new products are recognized in subsequent scans. For more information, see [Chapter 6, “Creating Local Software Products,”](#) on page 49. To configure the file types, do the following:

- ♦ To search for files with an .exe extension, select the **Collect.EXE Files** option.
- ♦ To search for files with a different extension, specify the extension in the **Additional Extensions** field. Separate each extension with a + sign, for example, com+dll.
- ♦ To scan for particular file types, select from the following:
 - ♦ **System:** Select this option to search for system files. This category is selected by default.
 - ♦ **Ancillary Application:** Select this option to search for files that are ancillary to, or associated with, a product that is recognized by the ZENworks Knowledgebase. This option is useful to create a comprehensive scan. This category is selected by default.
 - ♦ **Other:** Select this option to search for all other files. This category is selected by default.
- ♦ To include directories with products that are recognized by the ZENworks Knowledgebase, select **Include directories with recognized products**. This is useful to create a comprehensive scan.
- ♦ To limit the scope of the scan by including and excluding files and paths, configure which files and paths to include or exclude from the collection by using **Add** and **Remove** to specify which files and paths you want to include and exclude from the scan. You can edit the files and paths in the list by selecting the file or path and clicking **Edit**. If you specify a file or path in the **Files and paths to include in collection** field, the scan is limited to just that

file or path. If a file or path is specified in the **Files and paths to exclude from collection** field, all files and paths are searched except the specified file or path. Paths specified in the **Software Applications** panel are also skipped.

NOTE: If you are specifying a path, you must include a trailing backslash (\). For example, if you want to include all .exe files in the dir directory, type C:\dir\.

- 8 In the Advanced panel, configure diagnostic settings.

NOTE: The Diagnostic Mode check box is applicable only for 11.4.3 or older ZENworks managed agents.

- 9 Click **Apply** or **OK**.

2.1.2 Configuring a Scan for Devices in a Folder

- 1 In ZENworks Control Center, click the **Devices** tab, then click the **Managed** tab.
- 2 Click **Details** next to the folder containing the devices you want to configure a scan for.
- 3 Click the **Settings** tab.
- 4 In the Settings panel, click **Inventory**.
- 5 In the **Catalog** list, click **Inventory**.
- 6 In the Inventory panel, click **Override settings**.

This overrides the Management Zone settings for these devices.

- 7 In the Scan Now panel, configure how to run an inventory scan.

For configuring an inventory scan, perform steps from [Step 7 on page 14](#) through [Step 9 on page 14](#) listed in [Section 2.1, "Configuring an Inventory Scan," on page 11](#).

2.1.3 Configuring an Inventory Scan for a Device

- 1 In ZENworks Control Center, click **Devices**, then click the **Managed** tab.
- 2 Click the folder containing the device you want to configure a scan for.
- 3 Click the device.
- 4 Click the **Settings** tab.
- 5 In the Settings panel, click **Inventory**.
- 6 In the **Catalog** list, click **Inventory**.
- 7 In the Inventory panel, click **Override settings**.

This overrides the Management Zone and folder settings for this device.

- 8 In the Scan Now panel, configure how to run an inventory scan.

For configuring an inventory scan, perform steps from [Step 7 on page 14](#) through [Step 9 on page 14](#) listed in [Section 2.1, "Configuring an Inventory Scan," on page 11](#).

2.2 Scheduling an Inventory Scan

This section shows you how to schedule an inventory scan. By default, the inventory schedule is already configured.

You can define the scan schedule settings at three levels:

- ♦ **Management Zone:** The settings are inherited by all device folders and devices. To schedule a scan for the Management Zone, see [Section 2.2.1, “Configuring an Inventory Scan Schedule for the Management Zone,” on page 15.](#)
- ♦ **Device Folder:** The settings are inherited by all devices contained within the folder or its subfolders. Overrides the Management Zone settings. To schedule a scan for devices in a folder, see [Section 2.2.2, “Configuring an Inventory Scan Schedule for Devices in a Folder,” on page 17.](#)
- ♦ **Device:** The settings apply only to the device for which they are configured. Overrides the settings at the Management Zone level and device folder level. To schedule a scan for a device, see [Section 2.2.3, “Configuring an Inventory Scan Schedule for a Device,” on page 18.](#)

2.2.1 Configuring an Inventory Scan Schedule for the Management Zone

- 1 In ZENworks Control Center, click **Configuration**, then in the Management Zone Settings panel, click **Inventory**.
- 2 Click **Inventory Schedule** in the category list.
- 3 In the **Schedule Type** field, select the type of schedule you want to use.
 - No Schedule:** No scan is scheduled. See [“No Schedule” on page 15.](#)
 - Date Specific:** Scans run on specified dates. See [“Date Specific” on page 15.](#)
 - Recurring:** Scans run on a recurring schedule. See [“Recurring” on page 16.](#)

Perform full scan after imaging a device

Select the check box to perform a full scan after imaging the device.

No Schedule

- 1 Select **No Schedule** in the **Schedule Type** field.
- 2 Click **Apply** or **OK**.

No automatic scans are configured.

Date Specific

- 1 Select **Date Specific** in the **Schedule Type** field.
- 2 Click the + icon to the right of the **Start Date(s)** field to open a calendar, then select a date. To select more than one date, click the + icon again. Click the - icon to delete a selected date.
- 3 (Optional) Select **Run event every year** to run a scan annually on the dates you selected.

- 4 (Optional) For some reason, if the event does not run on the schedule you configured, to trigger the event immediately, select **Process immediately if device unable to execute on schedule**.
- 5 Select whether you want the scan to start at a specified time or at a random time between a specified start and end time.
- 6 Specify a start time, and if you selected **Start at a random time between Start Time and End Time**, specify an end time.
- 7 (Optional) Select **Use Coordinated Universal Time (UTC)**. Recommended, if the management zone is across geographical locations.
- 8 Click **Apply** or **OK**.

Recurring

Select whether you want the scan to run when a device is refreshed, on certain days of the week, monthly, or at a fixed interval.

To run a scan when a device is refreshed:

- 1 Select **Recurring** in the **Schedule Type** field.
- 2 Select **When a device is refreshed**.
- 3 (Optional) If you want the scan to be delayed for a set time after a refresh, select **Delay execution after refresh** and specify the time in days, hours, and minutes.
- 4 Click **Apply** or **OK**.

To run a scan on certain days of the week:

- 1 Select **Recurring** in the **Schedule Type** field.
- 2 Select **Days of the week**.
- 3 Select the days on which you want the scan to run.
- 4 In the **Start Time** field, specify the time you want the scan to start.
- 5 Click **More Options**.
- 6 (Optional) For some reason, if the event does not run on the schedule you configured, to trigger the event immediately, select **Process immediately if device unable to execute on schedule**.
- 7 (Optional) Select **Use Coordinated Universal Time (UTC)**. Recommended, if the management zone is across geographical locations.
- 8 (Optional) If you want the scan to start randomly between a specified start and end time, select **Start at a random time between Start Time and End Time**, then specify an end time.
- 9 (Optional) If you want to restrict the scan to a certain date range, select **Restrict schedule execution to the following date range**, then specify the start and end dates.
- 10 Click **Apply** or **OK**.

To run a scan monthly:

- 1 Select **Recurring** in the **Schedule Type** field.
- 2 Select **Monthly**.

- 3 Select either **Day of the month** and specify a number between 1 and 31, **Last day of the month**, or select the configurable field where you can choose a combination of days of the month for a recurring scan.
- 4 In the **Start Time** field, specify the time you want the scan to start.
- 5 Click **More Options**.
- 6 (Optional) For some reason, if the event does not run on the schedule you configured, to trigger the event immediately, select **Process immediately if device unable to execute on schedule**.
- 7 (Optional) Select **Use Coordinated Universal Time (UTC)**. Recommended, if the management zone is across geographical locations.
- 8 (Optional) If you want the scan to start randomly between a specified start and end time, select **Start at a random time between Start Time and End Time**, then specify an end time.
- 9 (Optional) If you want to restrict the scan to a certain date range, select **Restrict schedule execution to the following date range**, then specify the start and end dates.
- 10 Click **Apply** or **OK**.

To run a scan at a fixed interval:

- 1 Select **Recurring** in the **Schedule Type** field.
- 2 Select **Fixed Interval**.
- 3 Specify the number of months, weeks, days, hours, and minutes in their respective fields.

NOTE:

- ♦ If a Satellite with Collection role is configured in the Management Zone, ensure that the scan interval is set such that the scan schedule is less frequent than the **Collection Roll-Up Schedule**.
 - ♦ Currently, **When a device is refreshed** Schedule Type is not effective for Inventory Scans.
-

- 4 Specify a start date by clicking the calendar icon and selecting a date.
- 5 In the **Start Time** field, specify the time you want the scan to start.
- 6 Click **More Options**.
- 7 (Optional) For some reason, if the event does not run on the schedule you configured, to trigger the event immediately, select **Process immediately if device unable to execute on schedule**.
- 8 (Optional) Select **Use Coordinated Universal Time (UTC)**. Recommended, if the management zone is across geographical locations.
- 9 (Optional) If you want to restrict the scan to a certain date range, select **Restrict schedule execution to the following date range**, then specify an end date and end time.
- 10 Click **Apply** or **OK**.

2.2.2 Configuring an Inventory Scan Schedule for Devices in a Folder

- 1 In ZENworks Control Center, click **Devices**, then click the **Managed** tab.
- 2 Click **Details** next to the folder containing the devices you want to configure an inventory scan schedule for.
- 3 Click the **Settings** tab.

- 4 In the Settings panel, click **Inventory**.
- 5 In the **Settings** list, click **Inventory Schedule**.
- 6 In the Inventory Schedule panel, click **Override settings**.
This overrides the Management Zone settings for these devices.
- 7 In the **Schedule Type** field, configure the schedule you want to use.
For configuring the schedule type, perform steps from [Step 3](#) through [Step 3 on page 14](#) listed in [Section 2.2.1, “Configuring an Inventory Scan Schedule for the Management Zone,”](#) on [page 15](#).

2.2.3 Configuring an Inventory Scan Schedule for a Device

- 1 In ZENworks Control Center, click **Devices**, then click the **Managed** tab.
- 2 Click the folder containing the device you want to configure an inventory scan schedule for.
- 3 Click the device.
- 4 Click the **Settings** tab.
- 5 In the Settings panel, click **Inventory**.
- 6 In the **Settings** list, click **Inventory Schedule**.
- 7 In the Inventory Schedule panel, click **Override settings**.
This overrides the Management Zone and folder settings for this device.
- 8 In the **Schedule Type** field, configure the schedule you want to use.
For configuring the schedule type, perform steps from [Step 3 on page 15](#) through [Step 3 on page 14](#) listed in [Section 2.2.1, “Configuring an Inventory Scan Schedule for the Management Zone,”](#) on [page 15](#).

2.3 Running an Inventory Scan

You can run a scan four different ways:

- ♦ Using a device Quick Task
- ♦ Using a device task
- ♦ Using the ZENworks Icon menu (this runs a scan of the local machine only)
- ♦ Using a schedule

To run an inventory scan using a Quick Task:

- 1 In ZENworks Control Center, click **Devices**, then click the **Managed** tab.
- 2 Click the folder with the desired device(s) and select one or more devices that you want to inventory.
- 3 Click **Quick Tasks > Inventory Scan**.
- 4 In the **Inventory Scan** dialog box, select the preferred scan type
 - ♦ **Differential Inventory Scan:** Performs an inventory scan on the selected devices. This scan uploads only the differential data since the last scan to the server.

- ♦ **Complete Inventory Scan:** Performs a complete scan on the selected devices. This scan uploads the entire scan data to the server.

The latest inventory scan data will be uploaded to the server as per the upload schedule set by the administrator.

To run an inventory scan using a device task:

- 1 In ZENworks Control Center, click **Devices**, then click the **Managed** tab.
- 2 Open the folder with the desired device and click the device.
- 3 In the device tasks panel, click **Server Inventory Scan** if it's a server; click **Workstation Inventory Scan** if it's a workstation.

To run an inventory scan using the ZENWorks Icon menu:

NOTE: This feature is only available if the **User Can Initiate Scan** option is selected on the Inventory configuration page. For more information, see [Section 2.1, "Configuring an Inventory Scan," on page 11](#).

- 1 Right-click the ZENworks Icon and select **Show Properties**.
- 2 Click **Inventory**.
- 3 Click **Scan Now**.
- 4 (Optional) Click **Refresh Page** to update scan times.

To run an inventory scan by using a schedule, see [Section 2.2, "Scheduling an Inventory Scan," on page 15](#).

2.4 Adding Hardware Products from ZENworks Control Center

In ZENworks Control Center, you can manually add a hardware product for a device if the hardware product has not been reported in the Inventory Report after the Inventory scan. You can add a hardware product in ZENworks Control Center, to map it with specific devices for tracking and easy usage. For example, mapping a specific printer to a specific device.

To manually add a hardware to a device:

- 1 Log in to ZENworks Control Center. Click **Devices** and then **Workstations**.
- 2 Select any of the workstations, then click the **Inventory** tab.
- 3 Click **Detailed Hardware/Software Inventory**.
- 4 Scroll down and click **Add Hardware**.
- 5 On the **Add Hardware** page, select the required hardware product from the hardware products listed in the drop-down.
- 6 Fill in the required details for the selected hardware product, then click **Submit**.

The hardware products added to the device are displayed in the **Hardware** section of the Inventory report except **Logical Drive** and **Network Driver**. These are listed separately under the respective sections in the Inventory report.

Only the hardware products that are added manually to the device from ZENworks Control Center should have the delete and edit option on the Add Hardware page. To delete from the database the hardware product that is added to the device from the server, click Delete. To edit the hardware product that is added to the device from ZENworks Control Center, click Edit.

2.5 Viewing an Inventory Report for a Managed Device

A device's inventory includes information on hardware, software, and demographic data, which is gathered in an inventory scan. You can view this report through ZENworks Control Center or by using the ZENworks Icon menu. To view the Detailed Hardware/Software Inventory report, enable the **View Detailed Inventory** rights setting from the Management Zone > **Device rights**.

- ♦ [Section 2.5.1, "Using ZENworks Control Center to View a Managed Device's Inventory," on page 20](#)
- ♦ [Section 2.5.2, "Using the ZENworks Icon Menu to View a Managed Device's Inventory," on page 20](#)

2.5.1 Using ZENworks Control Center to View a Managed Device's Inventory

- 1 In ZENworks Control Center, click **Devices**.
- 2 Click the **Managed** tab.
- 3 Click the folder containing the device you want to view the inventory for.
- 4 Click the desired device.
- 5 Click the **Inventory** tab.

The Summary panel shows basic inventory information.

- 6 Click **Detailed Hardware/Software Inventory** for a complete inventory report.

This report shows detailed information about the device, including demographic data, hardware information, and software. From this page, you can click the various links to get more detailed information about the device.

Check the **History** tab, to view the changes made on the device. The software or hardware creation dates are based on the scan file processed on the server. If you have set a weekly scan on the device for a certain day of the week, the change history shows the changes made between two successive scans, with the date the scan is run. Only hotfix components show the actual install date for the particular device.

You can export the report to Excel, CSV, or PDF formats. You can also edit selected data. For more information, see [Section 2.6, "Editing a Managed Device's Inventory Data," on page 21](#).

2.5.2 Using the ZENworks Icon Menu to View a Managed Device's Inventory

- 1 Right-click the ZENworks icon and select **Show Properties**.
- 2 Click **Inventory**.
- 3 Click **View Inventory Details**.

2.6 Editing a Managed Device's Inventory Data

To edit the Detailed Hardware/Software Inventory report, you should enable the **Modify** setting on the View Detailed Inventory rights page from the Management Zone > **Device rights**.

- 1 Open the Detailed Hardware/Software Inventory report as shown in [Section 2.5, “Viewing an Inventory Report for a Managed Device,”](#) on page 20.

- 2 Click **Edit**.

- 3 Add or edit information on the Edit Workstation page.

User: Basic information about the user, including name, phone, and so on.

Reference: Inventory type, serial number, and asset tag. These values cannot be changed.

Workstation: Basic information about the workstation, including site, department, and so on.

Click the icon on the right to create a list of responses. Click the calendar icon next to the **Lease Expiration Date** field to choose a date.

- 4 Click **Submit**.

The data is added to the inventory report.

3 Scanning Inventory Only Devices

An inventory only scan allows you to scan devices in the zone that don't have the ZENworks Agent installed but do have the Inventory Only Module installed.

NOTE: License information cannot be tracked for software installed on inventory only devices. License information can only be tracked on managed devices on which the ZENworks Asset Management component is enabled.

For information on installing the Inventory Only Module, see the [ZENworks Discovery, Deployment, and Retirement Reference](#).

The following sections provide information on inventory only scans:

- ♦ [Section 3.1, “Configuring an Inventory Only Scan,” on page 23](#)
- ♦ [Section 3.2, “Scheduling an Inventory Only Scan,” on page 25](#)
- ♦ [Section 3.3, “Viewing an Inventory Report for an Inventory Only Device,” on page 27](#)
- ♦ [Section 3.4, “Editing the Demographic Data of an Inventory Only Device,” on page 27](#)
- ♦ [Section 3.5, “Enabling Reconciliation,” on page 28](#)
- ♦ [Section 3.6, “Using the Portable Collector,” on page 28](#)

3.1 Configuring an Inventory Only Scan

An inventory only scan allows you to collect data from devices in the Management Zone that only have the Inventory Only Module installed. By default, the inventory settings are preconfigured.

To configure an inventory only scan:

- 1 Click **Configuration**, then in the Management Zone Settings panel, click **Inventory**.
- 2 Click **Inventory Only** in the category list.
- 3 In the Server Refresh Interval panel, set the interval time in days, hours, and minutes.

The server handles requests from devices that have the Inventory Only Module installed, providing files for the settings, scan schedule, and so on. The interval setting determines how often the server evaluates the next scan schedule and when to obtain other settings. The server needs to poll the database at frequent intervals to pass on any changes that affect the devices.

The refresh interval should be set so that refreshes occur more frequently than scans. The default is 15 minutes.

NOTE: Ensure that the time interval of the Collection Server sending over data to the Primary server is lesser than the time interval of the managed devices sending over data to the Collection Server. For example, if Managed device M1 sends data to Collection Server every 12 minutes, configure the Collection Server to send data to the Primary server every 8 minutes.

- 4 In the Device Refresh Interval panel, set the interval time in days, hours, and minutes.

The Device Refresh Interval determines when the device checks the server for a change in settings, the schedule for the next scan, the ZENworks Knowledgebase for inventory, and new agent executables.

The refresh interval should be set so that refreshes occur more frequently than scans and less frequently than server refreshes. The default is 12 hours.

- 5 In the Scan panel, configure how you want to run the scan.

Collect Software Applications: Select this option if you want to scan for software applications installed on the device. This setting is selected by default.

Collect Software File Information: Select this option if you want to scan for software file information that can be used to identify software products that are not recognized by the ZENworks Knowledgebase. If you plan to create Local Software Products and add them to the knowledgebase, this option must be selected. For more information, see [Chapter 6, “Creating Local Software Products,” on page 49](#).

Collect Demographic Data: Select this option to gather demographic data from an inventoried-only device. This data is gathered from a file on the local machine. For more information, see [Section 4.6, “Scanning Demographic Data on an Inventory Only Device,” on page 38](#).

Run DMTF Translator: Select this option if you want to run the DMTF (Desktop Management Task Force) Translator. The DMTF translator converts the inventory data to formats that can be used by other tools and puts it on the local machine.

Collect MSI Information: Select this option if you want to scan for information about the installed Microsoft Installer (MSI) files that are used for installation, storage, and removal of programs on a device.

- 6 In the Software Applications panel, configure which directories to skip.

Skipping directories is useful in limiting the scope of the scan. The directories in the list are skipped.

- ♦ To add a directory, specify a directory in the **Skip Directories** field, then click **Add**.
- ♦ To edit an existing directory, select the directory, click **Edit**, edit the directory, then click **OK**.
- ♦ To delete an existing directory, select the directory and click **Remove**.

- 7 In the Software Files panel, configure which types of files to scan for.

Software applications discovered in an inventory scan are identified by specific files associated with the product. These identifications are kept in the ZENworks Knowledgebase. To identify products that aren't in the knowledgebase, you can search for files that are associated with an unrecognized product and use the file information to create a new product identification called a Local Software Product. This Local Software Product information can then be merged with the knowledgebase so that these new products are recognized in subsequent scans. For more information, see [Chapter 6, “Creating Local Software Products,” on page 49](#). To configure the file types, do the following:

- ♦ To search for files with an .exe extension, select the **Collect.EXE Files** option.
- ♦ To search for files with a different extension, specify the extension in the **Additional Extensions** field. Separate each extension with a + sign, for example, com+dll.
- ♦ To scan for particular file types, select from the following:
 - ♦ **System:** Select this option to search for system files. This category is selected by default.

- ♦ **Ancillary Application:** Select this option to search for files that are ancillary to, or associated with, a product that is recognized by the ZENworks Knowledgebase. This option is useful to create a comprehensive scan. This category is selected by default.
- ♦ **Other:** Select this option to search for all other files. This category is selected by default.
- ♦ To include directories with products that are recognized by the ZENworks Knowledgebase, select **Include directories with recognized products**. This is useful to create a comprehensive scan.
- ♦ To limit the scope of the scan by including and excluding files and paths, configure which files and paths to include or exclude from the collection by using **Add** and **Remove** to specify which files and paths you want to include and exclude from the scan. You can edit the files and paths in the list by selecting the file or path and clicking **Edit**. If you specify a file or path in the **Files and paths to include in collection** field, the scan is limited to just that file or path. If a file or path is specified in the **Files and paths to exclude from collection** field, all files and paths are searched except the specified file or path. Paths specified in the **Software Applications** panel are also skipped.

NOTE: If you are specifying a path, you must include a trailing backslash (\). For example, if you want to include all .exe files in the dir directory, type C:\dir\.

- 8 In the Advanced panel, configure diagnostic settings.

WARNING: These options are intended for advanced diagnostics. Use them only under the guidance of a Micro Focus Support representative.

- 9 In the Collection Servers panel, use the **Move Up** and **Move Down** buttons to arrange the collection servers.

This arrangement determines the order in which the collection servers receive the inventory data.

- 10 Click **Apply** or **OK**.

3.2 Scheduling an Inventory Only Scan

This section shows you how to schedule an inventory scan for an inventory only device. By default, the inventory schedule is already configured.

Unlike scans for managed devices, you can only define an inventory only scan for the entire Management Zone. In addition, you can run a scan only by using a schedule.

3.2.1 To Configure an Inventory Only Scan Schedule

- 1 In ZENworks Control Center, click **Configuration**, then in the Management Zone Settings panel, click **Inventory**.
- 2 Click **Inventory Only Schedule** in the category list.
- 3 In the **Schedule Type** field, select what type of schedule you want to use.
 - No Schedule:** No scan is scheduled. See [“No Schedule” on page 26](#).
 - Date Specific:** Scans run on specified dates. See [“Date Specific” on page 26](#).

Recurring: Scans run on a recurring schedule. See [“Recurring” on page 26](#).

No Schedule

- 1 Select **No Schedule** in the **Schedule Type** field.
- 2 Click **Apply** or **OK**.

No automatic scans are configured.

Date Specific

- 1 Select **Date Specific** in the **Schedule Type** field.
- 2 Click the + icon to the right of the **Start Date(s)** field to open a calendar, then select a date. To select more than one date, click the + icon again. Click the - icon to delete a selected date.
- 3 Specify a start time.
- 4 Click **Apply** or **OK**.

Recurring

Select whether you want the scan to run when a device is refreshed, on certain days of the week, monthly, or at a fixed interval.

To run a scan on certain days of the week:

- 1 Select **Recurring** in the **Schedule Type** field.
- 2 Select **Days of the week**.
- 3 Select the days on which you want the scan to run.
- 4 In the **Start Time** field, specify the time you want the scan to start.
- 5 Click **Apply** or **OK**.

To run a scan monthly:

- 1 Select **Recurring** in the **Schedule Type** field.
- 2 Select **Monthly**.
- 3 Select either **Day of the month** and specify a number between 1 and 31, **Last day of the month**, or select the configurable field where you can choose a combination of days of the month for a recurring scan.
- 4 In the **Start Time** field, specify the time you want the scan to start.
- 5 Click **Apply** or **OK**.

To run a scan at a fixed interval:

- 1 Select **Recurring** in the **Schedule Type** field.
- 2 Select **Fixed Interval**.
- 3 Specify the number of months, weeks, days, hours, and minutes in their respective fields.
- 4 Specify a start date by clicking the calendar icon and selecting a date.
- 5 In the **Start Time** field, specify the time you want the scan to start.

6 Click **Apply** or **OK**.

NOTE: Ensure that the **Collection Roll-Up Schedule** is more frequent than the scan interval if the Satellite with Collection role is configured in the Management Zone.

3.3 Viewing an Inventory Report for an Inventory Only Device

A device's inventory includes information on hardware, software, and demographic data, which is gathered in an inventory scan. To view the Detailed Hardware/Software Inventory report, enable the **View Detailed Inventory** rights setting from the Management Zone > **Inventoried Device** rights.

To view an inventoried-only device's inventory:

- 1 In ZENworks Control Center, click **Devices**.
- 2 Click the **Inventoried** tab.
- 3 Click the folder containing the device you want to view the inventory of.
- 4 Click the desired device.

The Inventory panel shows basic inventory information.

- 5 Click **Detailed Hardware/Software Inventory** for a complete inventory report.

This report shows detailed information about the device, including demographic data, hardware information, and software. From this page, you can click the various links to get more detailed information about the device.

Check the **History** tab, to view the changes made on the device. The software or hardware creation dates are based on the scan file processed on the server. If you have set a weekly scan on the device for a certain day of the week, the change history shows the changes made between two successive scans, with the date the scan is run. Only hotfix components show the actual install date for the particular device.

You can export the report to Excel, CSV, or PDF formats. You can also edit demographic data. For more information, see [Section 2.6, "Editing a Managed Device's Inventory Data," on page 21](#).

3.4 Editing the Demographic Data of an Inventory Only Device

To edit the Detailed Hardware/Software Inventory report, you should enable the **Modify** setting on the View Detailed Inventory rights page from the Management Zone > **Inventoried Device** rights.

- 1 Open the Detailed Hardware/Software Inventory report as shown in [Section 2.5, "Viewing an Inventory Report for a Managed Device," on page 20](#).
- 2 Click **Edit**.
- 3 Add or edit information on the Edit Workstation page.

User: Basic information about the user, including name, phone, and so on.

Reference: Inventory type, serial number, and asset tag. These values cannot be changed.

Workstation: Basic information about the workstation, including site, department, and so on. Click the icon on the right to create a list of responses. Click the calendar icon next to the **Lease Expiration Date** field to choose a date.

4 Click **Submit**.

The data is added to the inventory report.

3.5 Enabling Reconciliation

Inventory Only Reconciliation allows you to control whether and how new workstations are reconciled to avoid the possibility of duplicates in the database. When a scan is made of a workstation that is new to the Management Zone, it is assigned an identifier. If the identifier is lost, such as by a disk crash, it is assigned a new identifier during the next scan. Reconciliation allows you to check whether the workstation is already in the database. If it is, the identifier in the database is changed to match the new identifier.

You can use any or all of the following device attributes to identify a workstation for possible reconciliation:

- ♦ Serial Number
- ♦ MAC Address
- ♦ Machine Name

To enable inventory only reconciliation:

- 1 In ZENworks Control Center, click the Configuration tab.
- 2 In the Management Zone Settings panel, click **Inventory**.
- 3 In the **Category** list, click **Inventory Only Reconciliation**.
- 4 In the Auto-Reconcile Settings panel, select which device attributes you want to use for reconciliation.
 - ♦ Serial Number
 - ♦ Mac Address
 - ♦ Machine Name
- 5 Select **Enable Differentiation** to differentiate between workstations with the same identifier.
- 6 Click **Apply** or **OK**.

3.6 Using the Portable Collector

The Portable Collector is a standalone application that is used to inventory devices that rarely connect to the server or devices that do not have the ZENworks Agent installed. This data can then be imported into the Inventoried device list. When the data is imported, you can view and edit it just as you would an inventoried device. The Portable Collector can be run on Windows, Linux and OS X devices.

For more information, see the following:

- ♦ [Section 3.6.1, “Running the Portable Collector on a Windows Device,” on page 29](#)
- ♦ [Section 3.6.2, “Running the Portable Collector on an OS X Device,” on page 29](#)

- [Section 3.6.3, “Running the Portable Collector on a Linux Device,” on page 29](#)
- [Section 3.6.4, “Importing Data Gathered with the Portable Collector,” on page 30](#)

If you have any issues with the Portable Collector, see the [Appendix B, “Troubleshooting Asset Inventory,” on page 87](#) section.

NOTE: The Inventory Only scan settings are used when you create the Portable Collector. If you want the Portable Collector to scan for software files, for example, that option must be selected on the Inventory Only configuration page. For information on configuring an Inventory Only scan, see [Section 3.1, “Configuring an Inventory Only Scan,” on page 23](#).

3.6.1 Running the Portable Collector on a Windows Device

- 1 In the ZENworks Control Center, click **Devices**.
- 2 In the **Device Tasks** list, click **Create Portable Client**.
- 3 Save and uncompress the file.
- 4 Copy the Portable Collector files to a removable media, such as a CD or flash drive.
- 5 Take the Portable Collector to the device you want to inventory, then run `ZENCollector.exe` file in the Administrator mode.

The inventory XML (WIF) file will be created inside the `wif` folder.

- 6 Continue with [Section 3.6.4, “Importing Data Gathered with the Portable Collector,” on page 30](#).

3.6.2 Running the Portable Collector on an OS X Device

- 1 Navigate to `https://<zenworks_server or host_name>:port_number/zenworks-setup/`
- 2 Click **Inventory Tools**.
- 3 Click **osxportable.dmg** to download it to the desktop.
- 4 Mount the `osxportable.dmg` file.
- 5 Create a temporary folder, copy the contents of `osxportable`, which is available in the `/Volumes/osxportable` folder.
- 6 Open a terminal window (You must be a user with administrative privileges). Run `./zenumia-portable /full/path/to/output/directory`.

The inventory XML file (WIF) file be generated in the output directory folder.

- 7 Import the file into ZENworks Control Center as shown in [Section 3.6.4, “Importing Data Gathered with the Portable Collector,” on page 30](#).

3.6.3 Running the Portable Collector on a Linux Device

- 1 Navigate to `https://<zenworks_server or host_name>:port_number/zenworks-setup/`
- 2 Click **Inventory Tools**.
- 3 Click **Linux_Portable.tar.gz** to download it to the desktop.
- 4 Extract the `Linux_Portable.tar.gz` file.

- 5 Open a terminal window (You must be a user with administrative privileges). Run `./launch-portable-collector.sh`.
The inventory XML (WIF) file will be generated in the `final` directory.
- 6 Import the file into ZENworks Control Center as shown in [Section 3.6.4, “Importing Data Gathered with the Portable Collector,”](#) on page 30.

3.6.4 Importing Data Gathered with the Portable Collector

- 1 In ZENworks Control Center, click **Devices**.
- 2 In the **Device Tasks** list, click **Import Inventory**.
- 3 In the **Import Inventory** pop-up window, click **Browse**, select the inventory XML (WIF) file, and then click **OK**.

The inventoried device appears in the device lists in **Devices > Inventoried**, click the device name to see the inventory data.

4 Scanning Demographic Data

Inventory scans include demographic data that is gathered from workstation users through the use of the Collection Data Form. The Collection Data Form can be sent to a workstation user's computer with a prompt to fill out the data fields on the form. This data is then added to the inventory report for that workstation. This section includes the following topics:

- ♦ [Section 4.1, "Configuring the Collection Data Form," on page 31](#)
- ♦ [Section 4.2, "Deploying the Collection Data Form," on page 34](#)
- ♦ [Section 4.3, "Configuring the Collection Data Form Launch Schedule," on page 34](#)
- ♦ [Section 4.4, "Launching the Collection Data Form Using a Quick Task," on page 38](#)
- ♦ [Section 4.5, "Deploying the Data Collection Form Using a Device Task," on page 38](#)
- ♦ [Section 4.6, "Scanning Demographic Data on an Inventory Only Device," on page 38](#)

4.1 Configuring the Collection Data Form

When you configure the Collection Data Form, you are selecting what information you want to gather from the workstation user. The Collection Data Form is not configured by default. It must be configured before it can be deployed.

NOTE: Collection Data Form is not supported on Mac OSX managed devices.

You can define the Collection Data Form at three levels:

- ♦ **Management Zone:** The settings are inherited by all device folders and devices. To configure the Collection Data Form for the Management Zone, see [Section 4.1.1, "Configuring the Collection Data Form for the Management Zone," on page 32](#).
- ♦ **Device Folder:** The settings are inherited by all devices in the folder. Overrides the settings at the Management Zone level. To configure the Collection Data Form for a folder, see [Section 4.1.2, "Configuring the Collection Data Form for Devices in a Folder," on page 33](#).
- ♦ **Device:** The settings apply only to the device for which they are configured. Overrides the settings at the folder and Management Zone levels. To configure the Collection Data Form at the device level, see [Section 4.1.3, "Configuring the Collection Data Form for a Device," on page 33](#).

NOTE: If you are configuring the Collection Data Form settings on a device, you need to click **Override Settings** before you can change the system settings.

After it is configured and deployed, the Collection Data Form appears on the desktop of a managed device and prompts the workstation user to respond to a list of predefined questions.

For more information, see the following topics:

- ♦ [Section 4.1.1, “Configuring the Collection Data Form for the Management Zone,” on page 32](#)
- ♦ [Section 4.1.2, “Configuring the Collection Data Form for Devices in a Folder,” on page 33](#)
- ♦ [Section 4.1.3, “Configuring the Collection Data Form for a Device,” on page 33](#)

4.1.1 Configuring the Collection Data Form for the Management Zone

- 1 In ZENworks Control Center, click **Configuration**.
- 2 In the Management Zone Settings panel, click **Inventory**.
- 3 In the **Category** list, click **Collection Data Form**.
- 4 Specify any explanatory text for the workstation user in the **Introductory Text** field.
- 5 (Optional) If you want the Collection Data Form to be available to the workstation user to run at anytime, select **Show in ZENworks Icon Menu**.

This allows the workstation user to open the form by using the ZENworks Icon, and edit it as desired.

- 6 (Optional) Select **Show Cancel button on form** if you want to allow the workstation user to opt out of the process.
- 7 (Optional) Select **Invisible mode for autofill only** to populate the form with the autofill data. The form is hidden from the workstation user.
- 8 Select the data you want to gather, and configure how the workstation user can respond:

Label: Displays the name of the data you’re collecting, such as First Name.

Data Type: Specifies the data type: character, integer, decimal, or date.

Display: Displays the specified field on the Collection Data Form that is sent to the workstation user.

Editable: Enables the user to enter or edit a response in the specified field rather than being forced to accept the default value.

Required: Makes the response required. If a field is required, workstation users cannot submit the form until they enter the required data.

Autofill: Shows whether **Autofill** is on or off. Click **No** (or **Yes**, as appropriate) to open the Autofill dialog box, where you can specify a registry key or environment variable to populate the **Collection Data Form** field with the data that the registry key or variable points to, such as HKLM\SYSTEM\CurrentControlSet\Services\Eventlog\ComputerName for this registry key, or WinDir for this environment variable. You can also use a registry key with a space in it, such as HKEY_CURRENT_USER\Control Panel\Screen Saver.Stars\Density.

When the auto-fill field is empty, and if the editable field is enabled then user entered value is not considered.

While specifying for the autofill information for registry keys, you can either specify the short name or the complete key name.

For example, "HKCR" or "HKEY_CLASSES_ROOT", "HKCU" or "HKEY_CURRENT_USER", "HKLM" or "HKEY_LOCAL_MACHINE", "HKUSR" or "HKEY_USERS", "HKCF" or "HKEY_CURRENT_CONFIG".

Default: Specify any value you want to use as a default value.

Choice List: If there is more than one possible response, click **Edit** and specify the available responses. You can also choose to allow the workstation user to create entries by selecting **Allow user created entries**.

Edit Mask: Allows you to restrict how a user enters a response by selecting a format from the list in the **Edit Mask** field. The choices are phone, time, and currency.

Instructions: Add any instructions for the workstation user.

- 9 Click **Apply** or **OK**, or click **Reset** to revert to previous settings.

NOTE: You can also create custom fields, called administrator-defined fields, to gather additional data. For more information, see [Chapter 7, “Using Administrator-Defined Fields,” on page 57](#).

4.1.2 Configuring the Collection Data Form for Devices in a Folder

- 1 In ZENworks Control Center, click **Devices**.
- 2 In the Devices panel, click **Details** next to the folder whose devices you want to configure.
- 3 Click the **Settings** tab.
- 4 In the Settings panel, click **Inventory**.
- 5 In the Category panel, click **Collection Data Form**.
- 6 Click **Override settings**.

This overrides the Management Zone settings for these devices.

- 7 In the **Introductory Text** field, specify information to configure the Collection Data Form.

For configuring the Collection Data Form, perform steps from [Step 4 on page 32](#) through [Step 9 on page 33](#) listed in [Section 4.1.1, “Configuring the Collection Data Form for the Management Zone,” on page 32](#).

4.1.3 Configuring the Collection Data Form for a Device

- 1 In ZENworks Control Center, click **Devices**.
- 2 Click the **Managed** tab.
- 3 Click the folder that contains the device you want to configure.
- 4 Click the device.
- 5 Click the **Settings** tab.
- 6 In the Settings panel, click **Inventory**.
- 7 In the Catalog panel, click **Collection Data Form**.
- 8 Click **Override settings**.

This overrides the Management Zone and folder settings for this device.

- 9 In the **Introductory Text** field, specify information to configure the Collection Data Form.

For configuring the Collection Data Form, perform steps from [Step 4 on page 32](#) through [Step 9 on page 33](#) listed in [Section 4.1.1, “Configuring the Collection Data Form for the Management Zone,” on page 32](#).

4.2 Deploying the Collection Data Form

There are four ways you can deploy the Collection Data Form to a workstation:

- ♦ **Collection Data Form Schedule:** Using the Collection Data Form schedule deploys the form to all the workstations in the Management Zone. For more information, see [Section 4.3, “Configuring the Collection Data Form Launch Schedule,”](#) on page 34.
- ♦ **Device Quick Task:** Using a device Quick Task deploys the Data Collection Form to one or more workstation in a folder. For more information, see [Section 4.4, “Launching the Collection Data Form Using a Quick Task,”](#) on page 38.
- ♦ **Device Task:** Using a device task deploys the Data Collection Form to a specified workstation. For more information, see [Section 4.5, “Deploying the Data Collection Form Using a Device Task,”](#) on page 38.
- ♦ **Scheduled as part of an inventory scan:** Using the inventory scan schedule deploys the Collection Data Form to all the workstations in the Management Zone. For more information, see [Section 2.1, “Configuring an Inventory Scan,”](#) on page 11.

4.3 Configuring the Collection Data Form Launch Schedule

NOTE: If you selected **Show in ZEN Icon Menu** on the Collection Data Form configuration page, the Collection Data Form is always available to the workstation user to run at anytime. For more information, see [Section 4.1, “Configuring the Collection Data Form,”](#) on page 31.

You can define the schedule at three levels:

- ♦ **Management Zone:** The settings are inherited by all device folders and devices. To schedule the deployment of the Data Collection Form for the Management Zone, see [Section 4.3.1, “Configuring the Collection Data Form Launch Schedule for the Management Zone,”](#) on page 34.
- ♦ **Device Folder:** The settings are inherited by all devices in the folder. Overrides the settings at the Management Zone level. To schedule the deployment of the Data Collection Form for a device folder, see [Section 4.3.2, “Scheduling the Deployment of the Collection Data Form for Devices in a Folder,”](#) on page 37.
- ♦ **Device:** The settings apply only to the device for which they are configured. Overrides the settings at the Management Zone level. To schedule the deployment of the Data Collection Form for a device, see [Section 4.3.3, “Scheduling the Deployment of the Collection Data Form for a Device,”](#) on page 37.

4.3.1 Configuring the Collection Data Form Launch Schedule for the Management Zone

- 1 In ZENworks Control Center, click **Configuration**.
- 2 In the Management Zone Settings panel, click **Inventory > Collection Data Form Schedule**.
- 3 In the **Schedule Type** field, select the type of schedule you want to use to send out the Collection Data Form. You can select from the following options:

No Schedule: No deployment is scheduled. See [“No Schedule”](#) on page 35.

Date Specific: The Collection Data Form is deployed on specified dates. See [“Date Specific” on page 35](#).

Recurring: The Collection Data Form is deployed on a recurring schedule. See [“Recurring” on page 35](#).

No Schedule

- 1 Select **No Schedule** in the **Schedule Type** field.
- 2 Click **Apply** or **OK**.

The Collection Data Form is not scheduled to deploy.

Date Specific

To deploy the Collection Data Form on a specified date:

- 1 Select **Date Specific** in the **Schedule Type** field.
- 2 Click the + icon to the right of the **Start Date(s)** field to open a calendar, then select a date. To select more than one date, click the + icon again. Click the - icon to delete a selected date.
- 3 (Optional) Select **Run event every year** to deploy the Collection Data Form annually on the dates you selected.
- 4 (Optional) For some reason, if the event does not run on the schedule you configured, to trigger the event immediately, select **Process immediately if device unable to execute on schedule**.
- 5 Select whether you want to deploy the Collection Data Form at a specified time or at a random time between specified start and end times.
- 6 Specify a start time, and if you selected **Start at a random time between Start Time and End Time**, specify an end time.
- 7 (Optional) Select **Use Coordinated Universal Time (UTC)**. Recommended, if the management zone is across geographical locations.
- 8 Click **Apply** or **OK**.

Recurring

Select whether you want to deploy the Collection Data Form when a device is refreshed, on certain days of the week, monthly, or at a fixed interval.

To deploy the Collection Data Form when a device is refreshed:

- 1 Select **Recurring** in the **Schedule Type** field.
- 2 Select **When a device is refreshed**.
- 3 (Optional) If you want to delay deploying the Collection Data Form for a set time after a refresh, select **Delay execution after refresh** and specify the time in days, hours, and minutes.
- 4 Click **Apply** or **OK**.

To deploy the Collection Data Form on certain days of the week:

- 1 Select **Recurring** in the **Schedule Type** field.
- 2 Select **Days of the week**.

- 3 Select the days on which you want to deploy the Collection Data Form.
- 4 In the **Start Time** field, specify the time you want to deploy the Collection Data Form.
- 5 Click **More Options**.
- 6 (Optional) For some reason, if the event does not run on the schedule you configured, to trigger the event immediately, select **Process immediately if device unable to execute on schedule**.
- 7 (Optional) Select Use Coordinated Universal Time (UTC). Recommended, if the management zone is across geographical locations.
- 8 (Optional) If you want to deploy the Collection Data Form at a random time between a specified start and end time, select **Start at a random time between Start Time and End Time**, then specify an end time.
- 9 (Optional) If you want to restrict the deployment of the Collection Data Form to a certain date range, select **Restrict schedule execution to the following date range**, then specify the start and end dates.
- 10 Click **Apply** or **OK**.

To deploy the Collection Data Form monthly:

- 1 Select **Recurring** in the **Schedule Type** field.
- 2 Select **Monthly**.
- 3 Select either **Day of the month** and specify a number between 1 and 31, **Last day of the month**, or select the configurable field where you can choose a combination of days of the month for a recurring schedule.
- 4 In the **Start Time** field, specify the time you want to deploy the Collection Data Form.
- 5 Click **More Options**.
- 6 (Optional) For some reason, if the event does not run on the schedule you configured, to trigger the event immediately, select **Process immediately if device unable to execute on schedule**.
- 7 (Optional) Select Use Coordinated Universal Time (UTC). Recommended, if the management zone is across geographical locations.
- 8 (Optional) If you want to deploy the Collection Data Form at a random time between a start and end time, select **Start at a random time between Start Time and End Time**, then specify an end time.
- 9 (Optional) If you want to restrict the deployment of the Collection Data Form to a certain date range, select **Restrict schedule execution to the following date range**, then specify the start and end dates.
- 10 Click **Apply** or **OK**.

To send out the Collection Data Form at a fixed interval:

- 1 Select **Recurring** in the **Schedule Type** field.
- 2 Select **Fixed Interval**.
- 3 Specify the number of months, weeks, days, hours, and minutes in their respective fields.
- 4 Specify a start date and time.
- 5 Click **More Options**.
- 6 (Optional) For some reason, if the event does not run on the schedule you configured, to trigger the event immediately, select **Process immediately if device unable to execute on schedule**.

- 7 (Optional) Select Use Coordinated Universal Time (UTC). Recommended, if the management zone is across geographical locations.
- 8 (Optional) If you want to restrict the deployment of the Collection Data Form to a certain date range, select **Restrict schedule execution to the following date range**, then specify an end date and end time.
- 9 Click **Apply** or **OK**.

4.3.2 Scheduling the Deployment of the Collection Data Form for Devices in a Folder

- 1 In ZENworks Control Center, click **Devices**.
- 2 Click **Details** next to the folder whose devices you want to configure.
- 3 Click the **Settings** tab.
- 4 In the Settings panel, click **Inventory > Collection Data Form Schedule**.
- 5 Click **Override settings**.
This overrides the Management Zone settings.
- 6 In the **Schedule Type** field, configure the schedule you want to use.
For configuring the schedule type, see [Configuring the Collection Data Form Launch Schedule for the Management Zone](#).

4.3.3 Scheduling the Deployment of the Collection Data Form for a Device

- 1 In ZENworks Control Center, click **Devices**, then click the **Managed** tab.
- 2 Click the folder containing the device you want to configure a schedule for.
- 3 Click the device.
- 4 Click the **Settings** tab.
- 5 In the Settings panel, click **Inventory**.
- 6 In the Catalog list, click **Collection Data Form Schedule**.
- 7 In the Inventory panel, click **Override settings**.
This overrides both the Management Zone and folder settings.
- 8 In the **Schedule Type** field, configure the schedule you want to use.
For configuring the schedule type, see [Section 4.3.1, “Configuring the Collection Data Form Launch Schedule for the Management Zone,” on page 34](#).

4.4 Launching the Collection Data Form Using a Quick Task

Using a device Quick Task deploys the Collection Data Form to one or more devices in a folder.

To deploy the Collection Data Form using a device Quick Task:

- 1 In ZENworks Control Center, click **Devices**.
- 2 Click the folder containing the device you want to inventory.
- 3 Select the device or devices you want to inventory.
- 4 Click **Quick Tasks > Inventory Wizard**.

The Quick Task Status dialog box shows the progress of the deployment. When complete, the Collection Data Form appears on the screen of the device or devices. You can stop the deployment by selecting the workstation and clicking **Stop**.

- 5 Click **Hide** to close the dialog box.

4.5 Deploying the Data Collection Form Using a Device Task

Using a device task deploys the Collection Data Form to a specified workstation.

To deploy the Collection Data Form using a device task:

- 1 In ZENworks Control Center, click **Devices**.
- 2 Click the folder containing the device you want to inventory.
- 3 Click the device you want to inventory.
- 4 In the **Device Tasks** list, click **Device Inventory Wizard**.

The Quick Task Status dialog box shows the progress of the deployment. When complete, the Collection Data Form appears on the screen of the device. You can stop the deployment by selecting the workstation and clicking **Stop**.

- 5 Click **Hide** to close the dialog box.

4.6 Scanning Demographic Data on an Inventory Only Device

Inventory Only Devices don't use the Collection Data Form to gather demographic data.

Demographic data for an Inventory Only device must be entered manually into a file named `demodata.txt` and saved on the device. This data is then gathered during an inventory scan.

You can scan for the demographic data only on Windows, Macintosh, and Linux.

To enable demographic data to be gathered from an Inventory Only device:

- 1 Create a file called `demodata.txt`.

The file should reside in the following location:

- ♦ For Windows, `C:\Program Files\Novell\ZENworks\bin`

- ♦ For Macintosh, /usr/local/novell/zenworks/umia
- ♦ For Linux, /opt/novell/zenworks/umia

2 Enter demographic data into the file using the format shown below.

The example below shows all the fields that can be included as well as various field formats; however, only those fields that are actually entered need to be in the file. Examples of field formats that are shown is as follows:

- ♦ nc_user.ADF10 shows how to enter a date
- ♦ nc_user.ADF11 shows how to enter a time
- ♦ nc_workstation.ADF10 shows how to enter currency
- ♦ nc_workstation.ASF11 shows how to enter a number (decimal or integer)

NOTE: Only those Administrator-Defined Fields that have been configured through ZENworks Control Center have data from this file stored.

```
[demodata]
nc_user.FirstName=John
nc_user.MiddleName=U
nc_user.LastName=Smith
nc_user.Email=jsmith@company.com
nc_user.Phone=(xxx) xxx-xxxx
nc_user.Phone2=(xxx) xxx-xxxx xxxx
nc_user.Fax=(xxx) xxx-xxxx
nc_user.ADF0=
nc_user.ADF1=
nc_user.ADF2=
nc_user.ADF3=
nc_user.ADF4=
nc_user.ADF5=
nc_user.ADF6=
nc_user.ADF7=
nc_user.ADF8=
nc_user.ADF9=
nc_user.ADF10=1963-07-04T00:00:00
nc_user.ADF11=01:45 pm
nc_user.ADF12=
nc_user.ADF13=
nc_user.ADF14=
nc_user.ADF15=
nc_user.ADF16=
nc_user.ADF17=
nc_user.ADF18=
nc_user.ADF19=
nc_workstation.Site=Utah
nc_workstation.Department=QA
nc_workstation.CostCenter=US98765
nc_workstation.Building=A
nc_workstation.Floor=3
nc_workstation.Room=Lab
nc_workstation.Phone=(xxx) xxx-xxxx
nc_workstation.ADF0=
nc_workstation.ADF1=
nc_workstation.ADF2=
nc_workstation.ADF3=
nc_workstation.ADF4=
nc_workstation.ADF5=
nc_workstation.ADF6=
nc_workstation.ADF7=
nc_workstation.ADF8=
nc_workstation.ADF9=
nc_workstation.ADF10=$ 2322.45
nc_workstation.ADF11=10.0
nc_workstation.ADF12=
nc_workstation.ADF13=
nc_workstation.ADF14=
nc_workstation.ADF15=
nc_workstation.ADF16=
nc_workstation.ADF17=
nc_workstation.ADF18=
nc_workstation.ADF19=
```

- 3 Save the file.
- 4 Configure and run un an Inventory Only scan as shown in [Section 3.1, “Configuring an Inventory Only Scan,” on page 23](#) and [Section 3.2, “Scheduling an Inventory Only Scan,” on page 25](#).

5 Importing Demographic Data

Importing demographic data is the process of automatically populating the Novell ZENworks database with demographic information from Microsoft Active Directory and Novell eDirectory. The demographic information is made up of the inventory data associated with users, workstations, or other entities.

For information on the supported versions of Microsoft Active Directory and Novell eDirectory, see [LDAP Directory Requirements](#).

This section includes the following topics:

- [Section 5.1, “Creating LDAP Import Tasks,” on page 41](#)
- [Section 5.2, “Executing LDAP Import Tasks,” on page 48](#)
- [Section 5.3, “Viewing or Editing LDAP Import Tasks,” on page 48](#)

5.1 Creating LDAP Import Tasks

- 1 In ZENworks Control Center, click **Configuration** > **Asset Inventory**.
- 2 In the LDAP Import Tasks panel, click **New** to launch the New LDAP Import Task Wizard.
- 3 Complete the wizard by using information from the following table to fill in the fields.

Wizard Page	Details
Define Details page	<p>Fill in the following fields:</p> <ul style="list-style-type: none">♦ Name: Provide a unique name for the import task. The name cannot include any of the following characters: / \ * ? : " ' < > ` % ~ <p>If you want to use numeric characters in a name, you must include characters like <code>_</code>, <code>#</code>, or <code>^</code> between the name and numeric value. A numeric value cannot immediately follow an alphabetic character. For example, if there is an existing task named <code>ABC</code>, you can create a new task with a name <code>ABC_1</code> but not <code>ABC1</code>.</p> <ul style="list-style-type: none">♦ Description: Provide a short description for the import task. This description is displayed in the LDAP Import Task Details panel of ZENworks Control Center.

Wizard Page	Details
Enter LDAP Settings page > Search pre-configured LDAP source option	<p>The Enter LDAP Settings page lets you identify the LDAP directory against which you want to perform the import task.</p> <p>A preconfigured LDAP source is one that has already been defined as a user source in your Management Zone. For information on how to create a user source, see “Adding User Sources” in the ZENworks User Source and Authentication Reference.</p> <p>If you want to create a new connection to the LDAP directory, see “Enter LDAP Settings page > Specify a new LDAP source option” on page 43.</p> <p>To use an existing connection to the LDAP directory:</p> <ol style="list-style-type: none"> 1. Select Search pre-configured LDAP source from the drop-down list. 2. In the Source to Search list, select the LDAP source you want to search. <p>The Source to Search list contains only the directories that have been defined as user sources within your Management Zone.</p>

Wizard Page	Details
Enter LDAP Settings page > Specify a new LDAP source option	<p data-bbox="662 220 1385 279">The Enter LDAP Settings page lets you create a new connection to the LDAP directory to import inventory information.</p> <p data-bbox="662 308 1385 367">A new LDAP source is one that was defined as a new source when the import task was created.</p> <p data-bbox="662 396 1385 455">If you want to use an existing connection, see “Enter LDAP Settings page > Search pre-configured LDAP source option” on page 42.</p> <p data-bbox="662 485 1203 512">To create a new connection to the LDAP directory:</p> <ol data-bbox="683 520 1385 594" style="list-style-type: none"> <li data-bbox="683 520 1385 548">1. Select Specify a new LDAP source from the drop-down list. <li data-bbox="683 562 1385 594">2. Fill in the following fields: <p data-bbox="719 609 1385 667">LDAP Server: Provide the IP address or DNS hostname of the server that has the LDAP directory installed.</p> <p data-bbox="719 682 1385 808">LDAP Port: Select the LDAP port number. The default is the standard SSL port (636) or non-SSL port (389), depending on whether this option is enabled or disabled. If your LDAP server is listening on a different port, select that port number.</p> <p data-bbox="719 823 1385 949">LDAP Root Context: Provide the root context to establish the entry point in the directory. If you do not provide a root context, the directory’s root container becomes the entry point.</p> <p data-bbox="719 963 1385 1089">Credentials: Provide the credentials to acquire read-only access to the directory. You can have more than read-only access, but read-only access is all that is required and recommended.</p> <p data-bbox="719 1104 1385 1163">When accessing eDirectory, ensure that the account has read rights to the following:</p> <ul data-bbox="743 1178 1385 1283" style="list-style-type: none"> <li data-bbox="743 1178 1385 1236">♦ WM:NAME DNS attributes on the workstation and server objects <li data-bbox="743 1251 1385 1283">♦ All those attributes you want to import <p data-bbox="719 1297 964 1325">To add the credentials:</p> <ol data-bbox="740 1339 1385 1850" style="list-style-type: none"> <li data-bbox="740 1339 1385 1398">a. Click Add to display the Enter Credential Information dialog box. <li data-bbox="740 1413 1385 1440">b. In the Type drop-down list, select LDAP. <li data-bbox="740 1455 1385 1514">c. In the Username field, specify the appropriate username. <p data-bbox="776 1535 1385 1629">For Novell eDirectory access, use standard LDAP notation. For example, cn=admin_read_only,ou=users,o=mycompany</p> <p data-bbox="776 1644 1385 1738">For Microsoft Active Directory access, use standard domain notation. For example, AdminReadOnly@mycompany.com</p> <li data-bbox="740 1753 1385 1812">d. In the Password and Reenter Password fields, specify the user password. <li data-bbox="740 1827 1385 1850">e. Click OK. <li data-bbox="683 1871 1385 1929">3. (Optional) To save the credentials, select the Save credentials to datastore option. <p data-bbox="719 1944 1385 2003">The saved credentials are encrypted in the database for increased security.</p>

Wizard Page	Details
	<p>Credentials that are not saved are cleared from memory when the ZENworks Server is restarted. If you are creating a scheduled import task, you should save the credentials to ensure that they are still available when the import task is performed.</p> <p>IMPORTANT: If an optional field is defined in the LDAP directory, it must be included in the <code>dirimport.xml</code> file on the ZENworks Server to make it available in the LDAP Fields list. For more information, see “Optional fields are not visible in the LDAP Fields list in ZENworks Control Center” on page 93.</p>

Wizard Page	Details
Map Fields page > Key option	<p>The Map Fields page displays the LDAP directory fields on the left and ZENworks Inventory fields on the right. The ZENworks Inventory Fields list displays the following information:</p> <ul style="list-style-type: none"> ♦ A small subset of possibly hundreds of classes defined in your LDAP source, showing only those relevant to ZENworks Asset Inventory. ♦ All the Workstation and User administrator-defined fields. <p>The Key option lets you define a key assignment for the LDAP Import task. You must define a key assignment for each task to uniquely identify the mapped fields. You can define only one key for each task.</p> <p>Key is a unique value that is assigned by mapping an LDAP field to a unique ZENworks Inventory field. When a task runs, the key field is searched for the stored key value. If the key is unique, the data from the specified LDAP fields is imported to the specified ZENworks Inventory fields. If the key is not unique, only the first hit is selected for mapping, which might result in incorrect mappings.</p> <p>To define a key assignment:</p> <ol style="list-style-type: none"> 1. In the LDAP Fields list, locate the field. 2. In the ZENworks Inventory Fields list, select a corresponding key field from a similar class. <p>All workstation-based LDAP fields can be mapped only to the ZENworks Inventory fields belonging to a Device class. Similarly, all user-based LDAP fields can be mapped only to the ZENworks Inventory fields belonging to a User class. Thus, you need to create two independent tasks for workstation-based and user-based fields.</p> <p>For example, while importing data from Active Directory, you want to define a key for the LDAP field called name belonging to a computer class (which is unique across the organization). You can select the ZENworks Inventory field called Machine Name belonging to a Device class.</p> 3. Click Key. <p>After you define a key, “= [LDAP Fields class] / [LDAP Fields name]” is appended to the selected ZENworks Inventory field.</p> <p>For example, if you want to define the LDAP field called name belonging to a computer class and the ZENworks Inventory field called Machine Name belonging to a Device class as the key fields, the Inventory Device class Machine Name field changes to Machine Name = computer / name.</p>

Wizard Page	Details
Map Fields page > Map option	<p>The Map option lets you map one or more LDAP directory fields to the corresponding fields in the ZENworks Inventory database.</p> <p>To map an LDAP directory field to the corresponding ZENworks Inventory field:</p> <ol style="list-style-type: none"> 1. In the LDAP Fields list, locate a field you want to map. 2. In the ZENworks Inventory Fields list, select a corresponding field from a similar class. <p>All workstation-based LDAP fields can be mapped only to the ZENworks Inventory fields belonging to a Device class. Similarly, all user-based LDAP fields can be mapped only to the ZENworks Inventory fields belonging to a User class. Thus, you need to create two independent tasks for workstation-based and user-based fields.</p> <p>For example, while importing data from Active Directory, you want to map the LDAP field called displayName belonging to a user class. You can map it to the ZENworks Inventory field called First Name belonging to a User class.</p> 3. Click Map. <p>After you map the fields, “<- [LDAP Fields class] / [LDAP Fields name]” is appended to the selected ZENworks Inventory field.</p> <p>For example, if you want to map the LDAP field called displayName belonging to a user class to the ZENworks Inventory field called First Name belonging to a User class, the ZENworks Inventory User class First Name field changes to First Name <- user / displayName.</p> <p>If the size of the selected LDAP field exceeds the size of the corresponding ZENworks Inventory field, the data is truncated to the maximum size of storage and an error message is displayed in the Last Import Messages column. For more information on the error, see the <code>loader-messages.log</code> file located in the <code>%ZENWORKS_HOME%\logs\</code> directory on Windows or see the <code>/var/opt/novell/log/zenworks/loader-messages.log</code> file on Linux.</p> 4. (Optional) To map additional fields, repeat Step 1 through Step 3.

Wizard Page	Details
Map Fields page > Remove option	<p>To remove a field mapping:</p> <ol style="list-style-type: none"> 1. In the ZENworks Inventory Fields list, click a mapped field that you want to remove. 2. Click Remove. <p>To remove a key assignment from the selected field:</p> <ol style="list-style-type: none"> 1. In the ZENworks Inventory Fields list, click a field that is defined as a key. 2. Click Remove. <p>You must again define a key to uniquely identify the mapped fields. For more information, see “Map Fields page > Key option” on page 45.</p>
Set the Import Schedule page	<p>Configure the schedule when you want to run the import task, then click OK.</p> <ul style="list-style-type: none"> ♦ To immediately run the task after it is created, click Now. ♦ To set up a schedule: <ol style="list-style-type: none"> 1. Click On a schedule, then select one of the following schedules: <ul style="list-style-type: none"> ♦ No Schedule: Indicates that no schedule has been set. The task does not run until a schedule is set or the task is manually launched. This is useful if you want to create the task and come back to it later to establish the schedule or run the task manually. ♦ Date Specific: Specifies one or more dates on which to run the task. ♦ Recurring: Identifies specific days each week, month, or on a fixed interval on which to run the task. <p>IMPORTANT: Ensure that you do not set the same schedule for multiple tasks. If done, the scheduled tasks might not run. For more information, see “LDAP import tasks remain in a pending state if they run simultaneously” on page 89.</p> 2. (Conditional) If you selected Date Specific or Recurring for the schedule, fill in the schedule’s fields. <p>For more information on the schedules, click the Help button.</p>
Select Primary Server page	Select the ZENworks Server that you want to perform the LDAP import task.

When you finish the wizard, the import task is listed in the LDAP Import Tasks panel. You can use the panel to monitor the status of the task. If the key is unique, the data from the LDAP fields is imported to the ZENworks Inventory fields based on the mapped assignments.

IMPORTANT: Before running a task, ensure that all the existing tasks are in a finished state. For more information, see the troubleshooting scenario [“LDAP import tasks remain in a pending state if they run simultaneously” on page 89.](#)

5.2 Executing LDAP Import Tasks

You can execute an LDAP import task in two ways:

Schedule - based: For a schedule based import task, you need to configure a schedule. For more information, see [“Set the Import Schedule page” on page 47.](#)

Manual: To manually execute an import task, perform the following steps:

- 1 In ZENworks Control Center, click **Configuration > Asset Inventory**.
- 2 In the LDAP Import Tasks panel, select the import task you want to execute.
- 3 Click **Action > Launch Import Task**.

5.3 Viewing or Editing LDAP Import Tasks

To view or edit the LDAP import task settings:

- 1 In ZENworks Control Center, click **Configuration > Asset Inventory**.
- 2 In the LDAP Import Tasks panel, click a task to view or edit its settings.

The **Summary** tab lists the settings configured for the task:

- ♦ **GUID:** Displays the task’s globally unique identifier (GUID), which is a randomly generated string that provides a unique identifier for the task. You cannot edit the GUID. It remains the same as long as the task exists.
 - ♦ **Description:** Displays the task’s description, if one was provided when the task was created. The description appears only in ZENworks Control Center.
 - ♦ **Primary Server:** Displays the name of the ZENworks Server that is assigned to perform the discovery task.
 - ♦ **Schedule:** Displays when the task is scheduled to run.
 - ♦ **Configured LDAP Server:** Displays the IP address of the server that hosts the LDAP-based directory server.
 - ♦ **Mappings:** Displays all the mapped and key assignments established between the LDAP directory and ZENworks Inventory fields.
- 3 (Conditional) If the information for a device is incorrect or insufficient, click **Edit** and manually change the details for the fields.

If you configure another LDAP server, some of the mapped and key assignments might become incorrect. In this case, you must verify the assignments and map the fields again.

For more information on how to map the fields, see [“Map Fields page > Map option” on page 46.](#)

For more information on how to define a key assignment, see [“Map Fields page > Key option” on page 45.](#)

6 Creating Local Software Products

The following sections provide information about Local Software Products:

- ♦ [Section 6.1, “Understanding Local Software Products,” on page 49](#)
- ♦ [Section 6.2, “Understanding the Local Software Products Panel,” on page 49](#)
- ♦ [Section 6.3, “Creating Local Software Products,” on page 50](#)
- ♦ [Section 6.4, “Consolidating Local Software Products,” on page 50](#)
- ♦ [Section 6.5, “Editing Product Information,” on page 51](#)
- ♦ [Section 6.6, “Updating the ZENworks Knowledgebase,” on page 53](#)
- ♦ [Section 6.7, “Creating a New Software Fingerprint Request,” on page 54](#)

6.1 Understanding Local Software Products

Software applications discovered in an inventory scan are identified by specific files associated with the product. These identifications are kept locally in the ZENworks Knowledgebase, which can be updated by downloading and installing the latest Product Recognition Update (PRU).

To identify products that aren't in the Knowledgebase, you can search for files that are associated with an unknown product and use the file information to create a new product identification called a Local Software Product. This Local Software Product information can then be merged with the knowledgebase so that these new products are recognized in subsequent scans.

6.2 Understanding the Local Software Products Panel

To access the Local Software Products panel, click **Configuration** in ZENworks Control Center, then click the **Asset Inventory** tab.

This panel shows Local Software Products that have already been created, along with the following details:

- ♦ **Manufacturer:** The manufacturer of the product.
- ♦ **Product:** The name of the product. Click the product name to open the Local Software Product Detail page where you can edit product and file details.
- ♦ **Version:** The product version.
- ♦ **File:** A list of files associated with the product.
- ♦ **Installations:** The number of installations of the Local Software Product in the Management Zone.

6.3 Creating Local Software Products

Local Software Products are created from software files associated with a product. Before you can create a Local Software Product, you need to run an inventory scan that has been configured to search for those files. For information on configuring and running an inventory scan, see [Chapter 2, “Scanning Managed Devices,” on page 11](#) and [Chapter 3, “Scanning Inventory Only Devices,” on page 23](#).

To create, edit, or delete a Local Software Product, you need the **Create/Delete Local Products** rights enabled from the Management Zone > **Zone rights**.

To create local software products:

- 1 In ZENworks Control Center, click **Configuration**, then click the **Asset Inventory** tab.
- 2 In the Local Software Products panel, click either **New > Create from Software Files by Machine** or **New > Create from Unique Software Files**.

Clicking **Create from Software Files** opens a report definition that you can run to list all the software files on each machine in the Management Zone according to the way the inventory scan was configured.

Clicking **Create from Unique Software Files** opens a report definition that you can run to list all the software files that are not associated with a known software product as identified in the ZENworks Knowledgebase. The files are identified using Version Recognition Block (VRB) product information.

- 3 Click **Run**.
- 4 Select the files you want to use to create Local Software Products.
This page also allows you to edit the report definition and export the records to Excel, CSV, and PDF formats. For more information on editing the report definition, see [Section 8.2.6, “Editing a Custom Report,” on page 68](#).

- 5 Click **Create Local Products**.

A dialog box appears, confirming that the products have been created.

- 6 Click **Close**.

The selected products appear in the Local Software Products panel on the Configuration page.

6.4 Consolidating Local Software Products

If you have several files in the Local Software Products panel that identify the same product, you can consolidate them into one.

To consolidate two or more files:

- 1 In ZENworks Control Center, click **Configuration**.
- 2 Click the **Asset Inventory** tab.
- 3 In the Local Software Products panel, select the files you want to merge.
- 4 Click **Action > Merge Selected Products**.
- 5 Select a target product in the **Target Product** field.

6 Click **OK**.

The target product is displayed with its component files, which are shown in the **File** column.

6.5 Editing Product Information

ZENworks Control Center allows you to edit both product naming data and product recognition data of a local software product. For more information, see the following sections:

- ♦ [Section 6.5.1, “Editing the Product Naming Data,” on page 51](#)
- ♦ [Section 6.5.2, “Editing the Product Recognition Data,” on page 52](#)

6.5.1 Editing the Product Naming Data

1 In ZENworks Control Center, click **Configuration**.

2 Click the **Asset Inventory** tab.

3 In the Local Software Products panel, click a product.

The Local Software Product Detail page shows details about the local software product and the files used to identify it. From here, you can edit the product information or the Version Recognition Block (VRB) data for the identifying files. If the file associated with the product does not contain Version Resource Block (VRB) information, the fields show “Unnamed.”

4 Edit the fields in the **Product Naming** section.

Manufacturer: The manufacturer of the product.

Product: The name of the product.

Version: The version of the product.

Category/Subcategory: The type of product. You can create your own categories and subcategories. For more information, see [Section 10.3, “Managing Product Categories and Subcategories,” on page 78](#).

Distribution: The type of distribution:

- ♦ Commercial
- ♦ Freeware
- ♦ Shareware
- ♦ Open Source
- ♦ Multiple
- ♦ Public Domain

License Type: The software product’s license type:

- ♦ Full
- ♦ Evaluation
- ♦ OEM
- ♦ Multiple
- ♦ Network License

Current Manufacturer: The product’s current manufacturer.

Use for Version Reporting: Select **Use for Version Reporting** to use the product version for recognition purposes. You can use either the product version or the file version for recognition purposes. If you want to specify a version in the **Version** field to be used in the product definition, specify a value and select **Use for Version Reporting**. You can use either the product version or the file version for identification. To use the file version, select **Version Reporting** in the Product Recognition section.

- 5 Click **Apply** or **OK**.

6.5.2 Editing the Product Recognition Data

- 1 In ZENworks Control Center, click **Configuration**.
- 2 Click the **Asset Inventory** tab.
- 3 In the Local Software Product panel, click a product.
- 4 In the **Product Recognition** section, select the file you want to edit. If you want to use the file version for version reporting instead of the product version, select **Version Reporting** for that file.
- 5 Click **Edit**.

- 6 Edit the **File Attributes** fields.

File: The name of the file.

Extension: The file's extension.

Size: The size of the file. Use the arrow icons to change the file size.

Date: The date the file was created. Click the calendar icon to select a different date.

- 7 Edit the Version Resource Block (VRB) data.

Company Name: The manufacturer of the file. To use this data as part of the recognition criteria, select **Use for recognition**.

Product Name: The name of the product. To use this data as part of the recognition criteria, select **Use for recognition**.

Product Version: The version of the product. To use this data as part of the recognition criteria, select **Use for recognition**. To use the product version instead of the file version for recognition, select **Report the version found here**.

File Version: The version of the file. To use this data as part of the recognition criteria, select **Use for recognition**. To use the file version instead of the product version for recognition, select **Report the version found here**.

Language: The associated language. The available languages are shown in the drop-down list.

- 8 Click **OK** on the Edit Product Recognition File page.
- 9 Click **OK** on the Local Software Product Detail page.

6.6 Updating the ZENworks Knowledgebase

The ZENworks Knowledgebase is updated in several ways:

- ♦ [Section 6.6.1, “Merging Local Software Products with the ZENworks Knowledgebase,” on page 53](#)
- ♦ [Section 6.6.2, “Updating the ZENworks Knowledgebase with the PRU,” on page 53](#)

The Knowledgebase Status panel (**Configuration > Asset Inventory**) shows the date of the latest Product Recognition Update (PRU) and if there are newly defined local software products ready to merge with the Knowledgebase.

6.6.1 Merging Local Software Products with the ZENworks Knowledgebase

After a Local Software Product is created, you can add it to the ZENworks Knowledgebase so that subsequent scans identify the product on devices. The Knowledgebase Status panel on the Asset Inventory page (**Configuration > Asset Inventory**) shows when there are products ready to be merged.

- 1 In ZENworks Control Center, click the **Configuration** tab.
- 2 Click the **Asset Inventory** tab.
- 3 In the Local Software Products panel, select any local product you want to merge.
- 4 Click **Action > Update Knowledgebase with Local Product Changes**. A message appears to remind you that updates should only be made after all local product changes are complete. For information on editing local product data, see Section 6.5, “Editing Product Information,” on page 76.
- 5 Click **OK** to merge the listed software products with the Knowledgebase.

NOTE: When you select a local product for merging, changes to other local products are also merged with the ZENworks Knowledgebase.

6.6.2 Updating the ZENworks Knowledgebase with the PRU

To make sure that your ZENworks Knowledgebase is up-to-date, ensure that the latest PRU is always deployed in your zone.

- 1 To download and deploy the latest PRU, log in to ZENworks Control Center, click **Configuration > System Updates**.
- 2 Click **Action > Check for Updates**. It might take some time to connect and get the request from the server.
- 3 The new PRU is visible on the System Updates page. To download the update, click **Action > Download Update**.
- 4 Verify that the update is in the directory where you downloaded it, then click **Action > Deploy PRU Now**.
- 5 To verify the status of the PRU, go to **Configuration**, then click **Asset Inventory > Knowledge Base Status**.

The Knowledge Base Status should be similar to the following graphic:

- 6 Refresh the server and the agent and run a scan.
- 7 Go to the Inventory Details page and verify that the required software appears in the inventory list.

6.7 Creating a New Software Fingerprint Request

Although, each monthly Product Recognition Update (PRU) release cycle identifies many new software applications, it is not practical to include every possible application that is released. Limitations include software being licensed, software that is not yet covered as part of our PRU focus, and software that is released by vendors that are not well-known. To bridge these gaps you can use the SWID (Software Identification) utility to collect the necessary metadata to create a new software fingerprint request.

If software is unrecognized after you deploy the latest PRU, you can use the utility to create a Software Identification (SWID) file of the unrecognized software and send it to the Novell Fingerprint Support Team zam_support@microfocus.com.

6.7.1 Working with the SWID Wizard

You can request a software fingerprint by using the SWID Wizard, which scans configured locations on a workstation and looks for information about a particular piece of software. The output files from this utility are then sent to Novell for inclusion in the monthly PRU releases.

The SWID Wizard can scan locations on a remote machine, but only if you are logged into both the machines. For example, if you are running the probe from machine A and are attempting to reach machine B, you must be logged into both machines with the same account.

- ♦ “Preparing to Use the SWID Wizard” on page 54
- ♦ “Using the SWID Wizard” on page 54
- ♦ “Posting the SWID File” on page 55
- ♦ “Verifying When New Software Is Included in the PRU” on page 56

Preparing to Use the SWID Wizard

- 1 Before initializing the SWID Wizard, start each application you intend to run the SWID Wizard on.
- 2 From the **Help** menu of each application, open the **About** screen and capture it as a screen shot.
- 3 Save this screen shot as a bitmap file.

Using the SWID Wizard

- 1 Download the SWID Wizard from the [Micro Focus Downloads website \(http://download.novell.com/Download?buildid=R91sP1U5Fuo~\)](http://download.novell.com/Download?buildid=R91sP1U5Fuo~).
- 2 Save the `SWIDWizard.exe` to a temporary directory.

- 3 Browse to the temporary directory and double-click `SWIDWizard.exe`. The Software Identification Wizard is displayed.
- 4 In the User Information dialog box, specify the following details:
 - 4a Company Name
 - 4b Email Address
 - 4c Path where the output files will be stored.
 - 4d Select **Automatically return output file to Novell** if you have Internet access from this machine, or deselect it if you do not. If the SWID needs to be stored locally rather than sent to the Novell Web site, ensure that the check box is deselected.
The SWID is stored in the path you indicated in [Step 4c](#).
 - 4e Click **Continue**.
- 5 In the Product Information dialog box, specify the following details:
 - 5a Select either **Local Machine** or **Remote Machine**.
 - 5b Paths where you want to search for software.
 - 5c Product Name
 - 5d Version
 - 5e Language
 - 5f Edition
 - 5g (Optional) To add text strings to search for additional information about the application, click the **Add Text** button and the text in the Add Text dialog box.
or
Remove text strings by selecting one or more strings and clicking the **Remove Text** button.
 - 5h (Optional) Serial Number
 - 5i Browse to and select the screen shot file you created in [“Preparing to Use the SWID Wizard” on page 54](#).
 - 5j (Optional) Provide comments as necessary.
 - 5k Click **Continue**.
- 6 Verify your information and click **Collect Product Info**.

Posting the SWID File

After the SWID is generated, it is automatically posted to an [FTP site \(ftp://ftp2.novell.com/partners/tally/swidwizard/\)](ftp://ftp2.novell.com/partners/tally/swidwizard/), if you enabled the check box as indicated in [Step 4d](#) of the User Information page. The SWID file along with the bitmap image can also be sent to zam_support@microfocus.com.

We monitor the FTP site and the `zam_support` inbox. When we receive a request we send an acknowledge to the customer mail ID that you provided in the SWID file. (See [Step 4b](#) of the User Information page).

A SWID must be posted before the 20th of the month to be included in the current PRU. Requests posted after the 20th of the month are included in next month's PRU.

Verifying When New Software Is Included in the PRU

A new PRU is released on the first day of each month. A list of new software that has been fingerprinted for the month is posted at the FTP site (<http://ftp2.novell.com/partners/tally/pru/TCAIIPrd.txt>).

You can also download the latest PRU from ZENworks Control Center. Click the PRU and access the Readme for <PRU Month Year PRU>.

7 Using Administrator-Defined Fields

The following sections provide information about ZENworks features and procedures for administrator-defined fields.

- ♦ [Section 7.1, “About Administrator-Defined Fields,” on page 57](#)
- ♦ [Section 7.2, “Creating an Administrator-Defined Field,” on page 57](#)
- ♦ [Section 7.3, “Removing Administrator-Defined Fields from Web Console Reports,” on page 59](#)

7.1 About Administrator-Defined Fields

Administrator-defined fields allow you to add custom fields to inventory data. There are four types of fields:

- ♦ **User:** Used for gathering demographic data about the workstation user through the Collection Data Form.
- ♦ **Workstation:** Used for gathering demographic data about the workstation through the Collection Data Form.
- ♦ **Component:** Used for defining inventory data about a component.
- ♦ **Product:** Used for defining inventory data about a product.
- ♦ **Network Device:** Used for defining custom data field for network devices.

The Administrator-Defined Fields panel shows the type of field and the number of defined values. When you create a **User** or **Workstation** field, it appears on the Collection Data Form as a field for workstation users to fill out. **Component** and **Product** field values are added to the properties of the component or product. You can change the field value of an individual component or product by performing a product or component search, clicking the product or component, and editing the field value on the Product Details page. For more information, see [Chapter 9, “Managing Component Data,” on page 75](#) and [Chapter 10, “Managing Product Data,” on page 77](#).

7.2 Creating an Administrator-Defined Field

Regardless of the type of administrator-defined field you want to create, the steps are the same, whether it is a **User**, **Workstation**, **Component**, or **Product** field.

- 1 In ZENworks Control Center, click **Configuration**, then click the **Asset Inventory** tab.
- 2 In the Administrator-Defined Fields panel, click the type of field you want to create: **User**, **Workstation**, **Component**, or **Product**.

The User Fields panel shows existing defined fields, along with the following information:

Name: The name of the field.

Data Type: The data type: character, integer, decimal, or date.

The date format depends on the Zenworks Control Center location that is used.

For instance:

- ♦ If you login using English, you need to enter date in the MM/DD/YYYY format
- ♦ If you login using French, you need to enter date in the DD/MM/YYYY format
- ♦ If you login using Chinese, you need to enter date in the YYYY-MM-DD format

Size: The number of alphanumeric characters. This applies only to character-type fields.

Edit Type: Specifies how the user enters a response. The values are **Edit**, **List**, and **Combo**.

Default Value: The value that is specified when the field is created.

Internal Name: The field's internal ID.

3 Click **New**.

4 Specify the following fields:

Type: Filled in by default depending on the type of field you selected.

Name: Name of the administrator-defined field. This field is required.

Default Value: The default value of the field.

Data Type: **Character**, **Integer**, **Decimal**, or **Date**. If you choose Date as the data type, then you need to enter the date in the MM/DD/YYYY format.

Size: The maximum number of alphanumeric characters allowed in the field. This applies only to character-type fields.

Edit Type: Allows greater flexibility in entering and selecting field values. There are three options:

- ♦ **Edit:** Allows the user to enter a value or edit the default value.
- ♦ **List:** Allows the user to select a value from a list of possible choices.
- ♦ **Combo:** Allows the user to enter a value or select from a list.

Edit Mask: Select a format from the **Edit Mask** field list to restrict how a value is entered. The choices are phone, time, and currency. This applies only to character-type fields.

5 Click **Next**.

6 If you chose **List** or **Combo** as the **Edit Type** in [Step 4 on page 58](#), specify a list of choice values and click **Next**.

6a Specify a value in the **Choice List Values** field.

6b Click **Add**. Repeat for additional values.

6c Repeat [Step 6a on page 58](#) and [Step 6b on page 58](#) for additional values.

6d (Optional) Select a value and click **Edit** to change it.


6e (Optional) Select a value and click **Remove** to remove it.

6f (Optional) Import a list of values by clicking **Import** and specifying a file in the **Import File** field.

7 Click **Finish** to create the new field.

7.3 Removing Administrator-Defined Fields from Web Console Reports

Deleting an administrator-defined field does not remove references from the Web console report definition. You must remove the references manually.

- 1 Log in to ZENworks Control Center and select the report to be removed.
- 2 In the Custom Report Definition Summary page, click **Edit**.
- 3 From the Available list in the right panel, click the administrator-defined field to select it.
- 4 Click  to remove the selected administrator-defined field reference.
- 5 Click **Save** to save the report definition.

8 Using Reports

Reports allow you to view and analyze inventory data from your Management Zone. ZENworks Control Center includes predefined reports you can run along with reports you can customize. This section includes the following topics:

- ♦ [Section 8.1, “Using Inventory Standard Reports,” on page 61](#)
- ♦ [Section 8.2, “Using Inventory Custom Reports,” on page 64](#)
- ♦ [Section 8.3, “Inventory Report Rights,” on page 70](#)
- ♦ [Section 8.4, “Administrator Rights,” on page 71](#)
- ♦ [Section 8.5, “Manually Adding New Device Manufacturer or Model to the Inventory Reports,” on page 71](#)
- ♦ [Section 8.6, “Running Scheduled Report,” on page 72](#)

NOTE: The reports will also include the mobile inventory details.

Hotfixes collected by ZENworks are retrieved by using various ways such as registry and WIM queries. Hence, more number of Hotfixes are shown by ZENworks when compared to the Hotfixes shown by Microsoft through the Control Panel.

NOTE: Microsoft provides multiple sources for Hotfixes that reports more than those displayed in the Control Panel.

8.1 Using Inventory Standard Reports

Standard or predefined reports scan your inventory data and arrange the data according to the report configuration. More information is available in the following topics:

- ♦ [Section 8.1.1, “Available Standard Reports,” on page 61](#)
- ♦ [Section 8.1.2, “Running a Standard Report,” on page 63](#)

8.1.1 Available Standard Reports

ZENworks Control Center includes several predefined reports you can use to analyze the inventory in your Management Zone. These reports are grouped into folders according to their function. The available folders and reports are as follows:

- ♦ **Device Lists (folder):** Reports focusing on device details.
 - ♦ **Devices by Machine / Login Name:** Lists all devices by machine and login name.
 - ♦ **Devices by Mfg / Model:** Shows a count of systems by manufacturer and model.
 - ♦ **Lease Details:** Shows leased devices by contract along with the expiration date.

- ♦ **Devices with Virtual Machines:** Shows devices with host virtual machines that have been scanned.
- ♦ **Duplicate Asset Tags:** Shows devices with duplicate asset tags.
- ♦ **Duplicate Machine Names:** Shows devices with duplicate machine names.
- ♦ **Duplicate Serial Numbers:** Shows devices with duplicate serial numbers.
The number of installations displayed on the report might not match with the count of workstations, as there might be multiple components with the same product ID for a single workstation and on drill down, unique values will be displayed.
- ♦ **Software Applications (folder):** Reports focusing on software applications.
 - ♦ **Antivirus Details:** Shows antivirus definition files with links to the devices where they are installed.
 - ♦ **Software Applications by Category:** Shows a count of installed software products grouped by category and subcategory.
 - ♦ **Software Applications by Manufacturer:** Shows a count of installed products grouped by manufacturer.
 - ♦ **Software Applications by OS and Product:** Shows a count of installed products grouped by operating system and product name.
 - ♦ **Duplicate Serial Numbers:** Shows software products that have multiple instances of the same serial number.
 - ♦ **High Bandwidth Applications:** Shows a count of high-bandwidth products, such as multimedia and file-sharing software.
 - ♦ **Hot Fix Details:** Shows hot fixes and security patches with links to descriptions of the fixes and patches and the machine that they were installed on.
 - ♦ **Microsoft Products:** Shows a count of installed Microsoft products grouped by classifications specific to Microsoft.
 - ♦ **Operating Systems:** Shows a count of devices grouped by the installed operating system.
 - ♦ **OS Service Packs:** Shows a count of devices grouped by operating system and service pack.
- ♦ **Software Files (folder):** Reports focusing on software files, grouping them by category, manufacturer, and device.
 - ♦ **Software Files by Category:** Shows a count of software files grouped by category (**All**, **Other**, **Ancillary**, and **System**) with links to lists of the files.
 - ♦ **Software Files by Manufacturer:** Shows a count of software files grouped by manufacturer with links to lists of the files.
 - ♦ **Software Files by Device:** Shows a count of software files grouped by device with links to lists of the files.
- ♦ **Hardware Components (folder):** Reports focusing on hardware data.
 - ♦ **BIOS:** Shows installed versions and release dates grouped by manufacturer.
 - ♦ **Hardware Components by Category:** Shows a count of installed hardware products by category and subcategory.
 - ♦ **Hardware Components by Manufacturer:** Shows a count of installed hardware products grouped by manufacturer.
 - ♦ **Disk Space:** Shows a count of devices with total disk space within a specific range.

- ♦ **Duplicate Serial Numbers:** Shows hardware products with the same serial number.
- ♦ **Free Disk Space:** Shows a count of devices with free disk space within specific ranges.
- ♦ **Memory Size:** Shows a count of devices grouped by RAM size.
- ♦ **Processors:** Shows a count of devices grouped by CPU speed.
- ♦ **Upgrade Readiness (folder):** Reports that help you determine which devices are ready for an upgrade.
 - ♦ **Memory Upgrade:** Lists devices along with data on memory and available slots.
 - ♦ **SLED 10 Ready / Not Vista Capable:** Shows devices ready for SUSE Linux Enterprise Desktop 10 that are not ready for Windows Vista.
 - ♦ **SLED 10 Ready / Not Vista Premium Ready:** Shows devices ready for SUSE Linux Enterprise Desktop 10 that are not ready for Windows Vista Premium.
 - ♦ **SUSE Enterprise Desktop:** Lists devices along with data showing whether the device is ready or not ready for SUSE Linux Enterprise Desktop.
 - ♦ **Windows 2003 Server:** Lists devices along with data showing whether the device is ready or not ready for Windows Server 2003.
 - ♦ **Windows Vista Capable:** Shows devices capable of running Windows Vista.
 - ♦ **Windows Vista Premium Ready:** Shows devices capable of running Windows Vista Premium.
 - ♦ **Windows XP Professional:** Shows devices along with data showing whether the device is ready or not ready for Windows XP Professional.

8.1.2 Running a Standard Report

- 1 In ZENworks Control Center, click **Reports**.
- 2 In the Inventory Standard Reports panel, click the folder containing the report you want to run. Reports are listed by name and description. For a list of reports and descriptions, see [Section 8.1.1, “Available Standard Reports,” on page 61](#).
- 3 (Optional) Select how you want to filter your search. You can limit the scope of the report data by any of the following:
 - ♦ **Zone:** Select **Zone** to collect data from the entire Management Zone.
 - ♦ **Folder:** Select **Folder** and specify a folder name to gather data about that folder.
 - ♦ **Group:** Select **Group** and specify a group name to gather data about that group.
 - ♦ **Demographic:** Select **Demographic**, then select the criteria you want to use to filter the data.
- 4 Click a report to run it. Click the various links on the report for additional information. You can export the report to an Excel, CSV, or PDF format by clicking the corresponding link. In some reports, you can also click **Graph** to view the data in a bar graph, pie chart, or line graph format.

8.2 Using Inventory Custom Reports

ZENworks Control Center allows you to create and run custom reports that you can use to analyze the inventory in your Management Zone.

NOTE: The Inventory Custom Reports will also include the mobile inventory details.

These sections provide more information:

- ♦ [Section 8.2.1, “Available Custom Reports,” on page 64](#)
- ♦ [Section 8.2.2, “Running a Custom Report,” on page 65](#)
- ♦ [Section 8.2.3, “Creating a Custom Report,” on page 66](#)
- ♦ [Section 8.2.4, “Scheduling a Custom Report and Sending Notifications,” on page 67](#)
- ♦ [Section 8.2.5, “Configuring E-mail Addresses,” on page 67](#)
- ♦ [Section 8.2.6, “Editing a Custom Report,” on page 68](#)
- ♦ [Section 8.2.7, “Moving a Custom Report,” on page 69](#)
- ♦ [Section 8.2.8, “Deleting a Custom Report or Folder,” on page 69](#)
- ♦ [Section 8.2.9, “Viewing Scheduled Reports by Date and Title,” on page 70](#)
- ♦ [Section 8.2.10, “Importing New Report Definitions,” on page 70](#)

8.2.1 Available Custom Reports

ZENworks Control Center includes several predefined reports you can use to analyze the inventory in your Management Zone. These reports are grouped into folders according to their function. The available folders and reports are as follows:

- ♦ **Hardware Components (folder):** Reports focusing on hardware components, such as BIOS and system details.
 - ♦ **BIOS and System Details:** Shows the BIOS details for all current systems.
 - ♦ **Hardware added or deleted in last 6 months:** Lists the hardware components in the Management Zone and shows the number of additions and deletions over the previous 6 months.
 - ♦ **USB devices added in last 30 days:** Shows the workstations that have had a USB device added in the previous 30 days.
 - ♦ **Workstations with memory deletions in last 30 days:** Shows the workstations that have had memory module deletions during the previous 30 days.
- ♦ **Local Product Creation (folder):** Reports focusing on software files that can be used to create Local Software Products. For more information on Local Software Products, see [Chapter 6, “Creating Local Software Products,” on page 49](#).

WARNING: If you rename, move or delete the `Local Product Creation` folder or its contents, you will not be able to create the Local Software Products.

- ♦ **Software Files by Machine:** Shows the software files on each machine. You can use this report to create Local Software Products.

- ♦ **Unique Software Files:** Shows the software files along with Version Resource Block (VRB) data. You can use this report to create Local Software Products.
- ♦ **Software Applications (folder):** Reports focusing on software applications, such as how many applications were added during a specified time.
 - ♦ **SW apps added in last 30 days (by product):** Shows the software applications that were added during the previous 30 days, grouped by product.
 - ♦ **SW apps added in last 30 days (by workstation):** Shows the software applications that were added during the previous 30 days, grouped by workstation.
 - ♦ **SW apps deleted in last 30 days (by product):** Shows the software applications that were deleted during the previous 30 days, grouped by product.
 - ♦ **SW apps deleted in last 30 days (by workstation):** Shows the software applications that were deleted during the previous 30 days, grouped by workstation.
 - ♦ **Workstations with antivirus software:** Shows the Windows workstations (not marked as deleted) with antivirus software installed.
 - ♦ **Workstations with suspicious software installed:** Shows the workstations with suspicious software installed.
 - ♦ **Workstations without antivirus software:** Shows the Windows workstations (not marked as deleted) without antivirus software installed.
- ♦ **Systems (folder):** Reports focusing on system details, such as how many systems were added during a specified time.
 - ♦ **Hosts of Virtual Machines:** Shows the systems that are hosting virtual machines.
 - ♦ **Systems added in last 90 days:** Shows the systems (Windows, UNIX/Linux) that were added to the inventory database during the last 90 days.
 - ♦ **Systems deleted in last 90 days:** Shows the systems (Windows, UNIX/Linux) that were deleted during the previous 90 days.
 - ♦ **Systems that have not loaded results in 90 days:** Shows the systems (Windows, UNIX/Linux) that have not been marked as deleted and have not loaded scan results during the previous 90 days.
 - ♦ **Systems with less than 100 MB free space:** Shows the systems (Windows, UNIX/Linux) that have not been deleted and have less than 100MB free disk space.
 - ♦ **Systems with less than 128 MB memory:** Shows the systems (Windows, UNIX/Linux) that have not been deleted and have less than 128MB total memory.
 - ♦ **Virtual Machines:** Shows the virtual machines in your Management Zone.

8.2.2 Running a Custom Report

- 1 In ZENworks Control Center, click **Reports**.
- 2 In the Inventory Custom Reports panel, click the folder containing the report you want to run. The number of reports in each folder is shown in the **Report Count** column.
- 3 Click a report.
- 4 Click **Run** in the lower left corner.

On the report page, click the various links on the report for additional information. You can export the report to an Excel, CSV, or PDF format by clicking the corresponding link.

8.2.3 Creating a Custom Report

- 1 In ZENworks Control Center, click **Reports**.
- 2 In the Inventory Custom Reports panel, click the folder where you want to save the report, or create a new folder by clicking **New**, specifying a folder name, then clicking **OK**.
- 3 Click **New**.
- 4 Specify a name in the **Name** field.
- 5 Select the report type. The types are:
 - ♦ Devices
 - ♦ Software Applications
 - ♦ Software Files
 - ♦ Hardware Components
 - ♦ License Management
- 6 Select the focus of the report. The options are:
 - ♦ Basic Device Attributes
 - ♦ Product Filtering
 - ♦ File Filtering
 - ♦ History
- 7 Click **Continue**.
- 8 Fill in the following fields:

Name: Specify the name of the report.

Folder: Select a folder where you want to save the report.

Description: Specify a description for your report.

Type: This field is display only. It shows the report type you selected.

Columns: From the list on the left, select what data you want to include in your report. Use the arrow icons to move the selected data to the list on the right. Use Ctrl+click to select more than one option at a time. Use the up and down icons to arrange how you want the data displayed.

Criteria: Select your filter criteria in the **Field**, **Operator**, and **Value** fields. Use the + icons to add filters; click the - icon to delete a filter. Click **OR** or **AND** to toggle back and forth between the two operators.

Summary Criteria: Select your summary filter criteria in the **Field**, **Operator**, and **Value** fields. Use the + icons to add filters; click the - icon to delete a filter. Click **OR** or **AND** to toggle back and forth between the two operators
- 9 Click **Save**.

8.2.4 Scheduling a Custom Report and Sending Notifications

You can schedule a report to run automatically and send out notifications to specified people when the report is ready. To schedule a report and configure notifications:

- 1 In ZENworks Control Center, click **Reports**.
- 2 In the Inventory Custom Reports panel, click the folder containing the report you want to schedule.
- 3 Click the report you want to schedule.
- 4 In the **Custom Report Definition Summary** Click **Schedule/Notification**.
- 5 Fill in the following fields:

Start Date: Click the calendar icon to specify a date on which the report should run for the first time.

Frequency: Select a schedule to run the report or send a notification: yearly, monthly, weekly, daily, once, or never. Irrespective of the day/date, the report follows the following schedule frequency:

- ♦ **Yearly:** Runs the report on the first day of the year at 12 AM.
- ♦ **Monthly:** Runs the report on the first day of the month at 12 AM.
- ♦ **Weekly:** Runs the report on the first day of the week (Sunday at 12 AM).
- ♦ **Daily:** Runs the report daily at 12 AM.
- ♦ **Once:** Runs the report only once on the specified **Start Date**.
- ♦ **Never:** Never runs the report.

Output: Select whether you want to store the report, send an e-mail notification that the report is ready, or both. You can also choose to store the results or send a notification only when matching records are found. For information on configuring e-mail addresses, see [Section 8.2.5, “Configuring E-mail Addresses,” on page 67](#).

Maximum Records: Specify the maximum number of records to store.

- 6 Click **Submit**.

The report is generated once after clicking the **Submit** button. The configured schedule is followed to generate the subsequent reports.

8.2.5 Configuring E-mail Addresses

You can send notifications to selected people when a custom report is run. To do this, you need to import the e-mail addresses of those you want to notify into ZENworks Control Center. For information on sending notifications, see [Section 8.2.4, “Scheduling a Custom Report and Sending Notifications,” on page 67](#).

The E-mail Addresses panel on the Configuration page allows you to import e-mail addresses that can be used to send notifications when a custom report is ready, as configured in the report definition. Previously imported e-mail addresses are listed in the panel, along with the user’s first, last, and middle name.

To import e-mail addresses:

- 1 In ZENworks Control Center, click **Configuration**.
- 2 Click the Asset Inventory tab.
- 3 In the E-mail Addresses Panel, click **Action > Manage E-mail Addresses**.
- 4 In the **Import From** field, select either **Inventory Data** or **Comma Separated File**.

If you select **Inventory Data**, the e-mail addresses found in an inventory scan will be imported. If you select **Comma Separated File**, specify the file location in the **E-mail Address File** field. Use the first name,middle name,last name,email address format to save the CSV file.

For example, if the name is Wen Zeng Hong and the email address is wzh@gmail.com, specify the file location as Wen,Zeng,Hong,wzh@gmail.com. If there is no middle name, Zeng, save the CSV file as Wen,,Hong,wzh@gmail.com.

- 5 Click **Import**.
- 6 Click **Close**.

To delete all e-mail information:

- 1 In ZENworks Control Center, click **Configuration**.
- 2 In the E-mail Addresses Panel, click **Action > Manage E-mail Addresses**.
- 3 Click **Delete**.
- 4 Click **OK**.

All e-mail information is deleted.

8.2.6 Editing a Custom Report

- 1 In ZENworks Control Center, click **Reports**.
- 2 In the Inventory Custom Reports panel, click the folder containing the report you want to edit.
- 3 Click the report.
- 4 Click **Edit** in the lower left corner.
- 5 Edit the following fields:

Name: The name of the report.

Folder: The folder where you want to save the report.

Description: The description for your report.

Type: This field is display only. It shows the report type you selected.

Columns: From the list on the left, select what data you want to include in your report. Use the arrow icons to move the highlighted data selection to the list on the right. Use Ctrl-click to select more than one option at a time. Use the up and down icons to arrange how you want the data displayed.

Criteria: Select your filter criteria in the **Field**, **Operator**, and **Value** fields. Use the + icons to add filters; click the - icon to delete a filter. Click **OR** or **AND** to toggle back and forth between the two operators.

Summary Criteria: Select your summary filter criteria in the **Field**, **Operator**, and **Value** fields. Use the + icons to add filters; click the - icon to delete a filter. Click **OR** or **AND** to toggle back and forth between the two operators.

6 Click **Save**.

8.2.7 Moving a Custom Report

- 1 In ZENworks Control Center, click **Reports**.
- 2 In the Inventory Custom Reports panel, click the folder containing the report or reports you want to move.
- 3 Select the report or reports you want to move.
- 4 Click **Edit > Move**.
- 5 Select a new folder location.
- 6 Click **OK**.

WARNING: If you move reports in the **Local Product Creation** folder, you will not be able to create the Local Software Products.

8.2.8 Deleting a Custom Report or Folder

To delete a custom report:

- 1 In ZENworks Control Center, click **Reports**.
- 2 In the Inventory Custom Reports panel, click the folder containing the report you want to delete.
- 3 Select the report you want to delete.
- 4 Click **Delete**.

To delete a folder:

- 1 In ZENworks Control Center, click **Reports**.
- 2 In the Inventory Custom Reports panel, select the folder you want to delete.
- 3 Click **Delete**.

WARNING:

- ♦ If you delete reports in the **Local Product Creation** folder, you will not be able to create the Local Software Products.
 - ♦ Deleting a folder deletes all the reports in that folder.
-

8.2.9 Viewing Scheduled Reports by Date and Title

Reports that are run on a schedule are stored in a database. You can view these reports either by title or date. For information on scheduling reports, see [Section 8.2.4, “Scheduling a Custom Report and Sending Notifications,” on page 67](#).

To view a scheduled report by date or title:

- 1 In ZENworks Control Center, click **Reports**.
- 2 In the Inventory Custom Reports panel, click one of the following:
 - ♦ **Action > View Scheduled Report Results by Date**
 - ♦ **Action > View Scheduled Report Results by Title**

The Scheduled Reports by Grouping page opens and shows the saved scheduled custom reports grouped by date or title and a report count. Click the date or title to open the **Scheduled Reports** page, where you can select a report and view it. To delete a group of reports, select the group and click **Delete**.

8.2.10 Importing New Report Definitions

If you have defined reports in ZENworks Asset Management 7.5, you can import them into ZENworks Control Center. You can also re-import reports that have been exported by ZENworks Control Center. A predefined XML format is needed for import.

To import report definitions:

- 1 In ZENworks Control Center, click **Reports**.
- 2 In the Inventory Custom Reports panel, click **Action > Import New Report Definition**.
- 3 Specify the file in the **Query import file** field, or click **Browse** to search.
- 4 Click **Import**.

8.3 Inventory Report Rights

Inventory Report Rights allows you to manage the administrator rights for each folder and its reports. Each report folder has rights associated with it, governing all the reports within that folder. For example, if you have full rights, you can edit a report; but with view/execute rights, you can only see the report and run it. With inventory report rights, you can limit who has access to certain reports and who has permission to edit them. The report folder type, custom or standard, and the report name are listed along with the rights associated with the folder. The choices are:

- ♦ **Remove all rights:** This removes all rights to the folder, so the specified administrator cannot see it.
- ♦ **Assign view/execute rights:** This allows the specified administrator to view and execute a report in the specified folder, but not to edit, move, or delete a report in that folder.
- ♦ **Assign full rights:** This gives the specified administrator full rights to create, edit, move, and delete reports. For standard reports, this setting is the same as **View/Execute**, because you cannot alter a standard report.

To change inventory report rights:

- 1 In ZENworks Control Center, click **Configuration**.
- 2 In the Administrators panel, click an administrator.
- 3 Click on the Rights tab.
- 4 In the Administrator Tasks panel on the left, click **Inventory Report Rights**.
- 5 Select the desired folders.
- 6 Click one of the following:
 - ♦ **Edit > Remove All Rights**
 - ♦ **Edit > Assign View/Execute Rights**
 - ♦ **Edit > Assign Full Rights**

The change is reflected in the **Rights** column.

8.4 Administrator Rights

Administrators now have access to change or assign the report rights. The Inventory Report Rights page allows you to configure the default rights settings that you can assign to a user. By default, a user has View/Execute Rights enabled. Changing this setting does not affect existing users whose default rights were already modified.

You can use either of the following settings as the default:

- ♦ No Rights
- ♦ View/Execute Rights

8.5 Manually Adding New Device Manufacturer or Model to the Inventory Reports

If any device manufacturer or model is not displayed in the inventory reports, perform the following:

Update the `system-models.properties` file.

- ♦ **On Windows:** `%ZENWORKS_HOME%/conf/`
- ♦ **On Linux:** `/etc/opt/novell/zenworks/`

NOTE: Before updating, ensure that you take a backup of the `system-models.properties` file.

The property file includes two section:

- ♦ **Manufacturers:** Lists all the available manufacturers. If needed, you can add new manufacturers.
- ♦ **Models:** Lists all the available device models separated by manufacturers.

NOTE: After updating the `system-models.properties` file, ensure that you perform Full Inventory scan on the agent.

8.5.1 To add a new model to an existing manufacturer

Based on the manufacturer's name, add the model number/name as shown in the below example.

Example: If the manufacturer name is already added, then just add the new model name:

```
dell=Latitude,OptiPlex,Inspiron,XPS, <new_model_name1>, <new_model_name2>
```

8.5.2 To add a new manufacturer and model

If the manufacturers name is not listed in the manufacturers list, then add a new manufacturer name in the manufacturers list separated by a comma and then add the model name/number.

Example:

```
manufacturers=acer,asus,dell,hp,lenovo,microsoft,samsung,<new_manufacturer_name>
```

After adding manufacturers list, add the model name or number as shown in the below example.

Example: <new_manufacturer_name>=<new_model_name1>, <new_model_name2>

NOTE: After updating the file, restart the zenloader service for the changes to get effective.

8.6 Running Scheduled Report

As an administrator, the server on which the scheduled report runs can be configured by inserting a record in ZopaqueData table with name as 'run.scheduled.reports' and data fields as a list of comma separated server GUIDs on which the reports have to be run.

Run the following query to add the 'run.scheduled.reports' entry in the zOpaqueData table:

```
insert into zopaquedata(object,name,data) values  
( 'zzenobjectid', 'run.scheduled.reports', 'serverGUID1,serverGUID2' );
```

The data in the database can be modified later by running the following query:

```
UPDATE zopaquedata  
SET data =( 'serverGUID1,serverGUID2' )  
WHERE name = 'run.scheduled.reports';
```

serverGUID1 and serverGUID2 are the GUIDs of servers on which the scheduled report should be run.

For the changes to take effect, you can either wait for an hour without restarting the ZENserver service or restart the ZENServer service for the changes to take effect immediately.

NOTE

- ♦ This entry in zOpaqueData governs only the inventory-scheduled reports and does not govern the custom reports, or predefined reports. These reports will continue to run in the existing method.
 - ♦ Earlier the schedules were checked every 10 minutes. Now we are checking for the servers that are listed in zOpaqueData only. In case no entry is created in zOpaqueData, the scheduled reports run on any server in the zone like earlier.
-

9 Managing Component Data

A component is a hardware or software product associated with a workstation, for example, a spreadsheet application or a network interface card. ZENworks Control Center allows you to list a workstation's components or find workstations with a particular component. After you locate the component, you can edit the component data, such as the product name and serial number. You can examine component data through component searches.

The following sections provide information about managing component data:

- ♦ [Section 9.1, “Searching for a Component and Viewing Component Data,” on page 75](#)
- ♦ [Section 9.2, “Editing the Component Data,” on page 76](#)

9.1 Searching for a Component and Viewing Component Data

Before you can view component data, you need to perform a component search. Component searches are done through the Component Search panel ([Configuration > Asset Inventory](#)).

The Component Search panel allows you to select filters and filter sets to search for a particular component, then lists the components along with the following information:

- ♦ **Machine Name:** The name of the machine that has the particular product.
- ♦ **Manufacturer:** The manufacturer of the product.
- ♦ **Product:** The name of the product.
- ♦ **Version:** The version of the product.
- ♦ **Category:** The product category.
- ♦ **Subcategory:** The product subcategory.

To search for a component and view component data:

- 1 In ZENworks Control Center, click [Configuration](#), then click the [Asset Inventory](#) tab.
- 2 In the Component Search panel, click [Add Filter](#) or [Add Filter Set](#), depending on the filtering model you want to use.
- 3 Select options for your filter.
For example, you could search by machine name or department.
- 4 (Optional) Create additional filters or filter sets.
- 5 Click [Search](#).

Components matching your search criteria are listed, along with additional information about the component.

9.2 Editing the Component Data

- 1 Search for a component, as shown in [Section 9.1, “Searching for a Component and Viewing Component Data,”](#) on page 75.
- 2 Click a product name to view the component details. To add new hardware or edit the serial number or asset tag of existing hardware, log in to the Inventory Collection Editor as an administrator from your managed device. For more information, see “Working with the Inventory Collection Editor” in the [ZENworks Agent Guide](#).

The Component Details panel opens, displaying the following details about the component, along with any administrator-defined fields:

- ♦ **Machine Name:** The name of the machine.
 - ♦ **Product:** The name of the product.
 - ♦ **Asset Tag:** The asset tag number.
 - ♦ **Serial Number:** The component’s serial number.
- 3 Click **Change Product** to open the Product Search window, where you can search for and select a new product name.
 - 4 Select your filter criteria, then click **Search**.
 - 5 Select a product from the list, then click **Select Product**.
 - 6 Edit the other fields as desired.
 - 7 Click **OK** or **Apply**.

9.2.1 Using Administrator-Defined Fields

You can add administrator-defined fields to the Component Details panel to show additional information about the component. For example, you could add a field called **Malfunctioning**, with a **Yes** or **No** choice selection to show the product’s working status. For more information on creating administrator-defined fields, see [Chapter 7, “Using Administrator-Defined Fields,”](#) on page 57.

10 Managing Product Data

A product is a piece of hardware or software identified by the manufacturer, product name, and model/version. ZENworks Control Center allows you to search for products, view details about the product, and classify products according to category and subcategory. The following sections provide more information about managing product data:

- ♦ [Section 10.1, “Searching for a Product and Viewing Product Data,” on page 77](#)
- ♦ [Section 10.2, “Reclassifying a Product,” on page 78](#)
- ♦ [Section 10.3, “Managing Product Categories and Subcategories,” on page 78](#)

10.1 Searching for a Product and Viewing Product Data

Before you can view product data, you need to perform a product search. Product searches are done through the Product Search panel ([Configuration > Asset Inventory](#)).

The Product Search panel allows you to select filters and filter sets to search for a particular product, then lists the product along with the following information:

- ♦ **Manufacturer:** The manufacturer of the product.
- ♦ **Product:** The name of the product.
- ♦ **Version:** The version of the product.
- ♦ **Category:** The product category.
- ♦ **Subcategory:** The product subcategory.

To search for a product and view product data:

- 1 In ZENworks Control Center, click [Configuration](#), then click the [Asset Inventory](#) tab.
- 2 In the Product Search panel, click [Add Filter](#) or [Add Filter Set](#), depending on the filtering model you want to use.
- 3 Select options for your filter.
For example, you could search by product category or type.
- 4 (Optional) Create additional filters or filter sets.
- 5 Click [Search](#).

Products matching your search criteria are listed, along with additional information about the product.

10.2 Reclassifying a Product

Products are classified by category and subcategory. To change product classification:

- 1 Search for a product as shown in [Section 10.1, “Searching for a Product and Viewing Product Data,” on page 77](#).
- 2 Click a product name to open the Product Details panel.
- 3 In the **Category/Subcategory** field, select a new category/subcategory pair.
For added flexibility, ZENworks Control Center allows you to create new category/subcategory pairs. For more information, see [Section 10.3, “Managing Product Categories and Subcategories,” on page 78](#).
- 4 Click **OK** or **Apply**.

10.3 Managing Product Categories and Subcategories

During an inventory scan, ZENworks Control Center uses a knowledgebase of thousands of products to identify scanned products. After they are identified, these products are classified by category and subcategory. For added flexibility, ZENworks Control Center allows you to reclassify products and create new product categories.

Categories and subcategories are managed through the Product Categories panel (**Configuration > Asset Inventory**). This panel displays the following information:

- ♦ **Category Type:** The product category, such as CPU or CD-ROM. These are predefined.
- ♦ **Category Name:** The name of the product category.
- ♦ **Source:** Specifies whether the category name is a default value (**Novell**) or a user-defined value (**Local**). Only **Local** categories can be edited or deleted.

The following sections provide more information about managing product categories and subcategories:

- ♦ [Section 10.3.1, “Creating a New Product Category,” on page 78](#)
- ♦ [Section 10.3.2, “Renaming a Product Category,” on page 79](#)
- ♦ [Section 10.3.3, “Deleting a Product Category,” on page 79](#)
- ♦ [Section 10.3.4, “Creating a New Product Subcategory,” on page 79](#)
- ♦ [Section 10.3.5, “Renaming a Product Subcategory,” on page 79](#)
- ♦ [Section 10.3.6, “Deleting a Product Subcategory,” on page 80](#)

10.3.1 Creating a New Product Category

- 1 In ZENworks Control Center, click **Configuration**, then click the **Asset Inventory** tab.
- 2 In the Product Categories panel, click **New**.
- 3 Select a category type in the **Category Type** field.
- 4 Specify a name in the **Category Name** field.

- 5 Click **OK**.

The new category is added to the category list with the source shown as **Local**. You can further define this category by assigning a subcategory. For more information, see [Section 10.3.4, “Creating a New Product Subcategory,”](#) on page 79.

10.3.2 Renaming a Product Category

- 1 In ZENworks Control Center, click **Configuration**, then click the **Asset Inventory** tab.
- 2 In the Product Categories panel, select the category you want to rename.
You can only rename categories whose source is **Local**.
- 3 Click **Edit > Rename**.
- 4 Specify a new name in the **Category Name** field.
- 5 Click **OK**.

10.3.3 Deleting a Product Category

- 1 In ZENworks Control Center, click **Configuration**, then click the **Asset Inventory** tab.
- 2 In the Product Categories panel, select the category you want to delete.
You can only delete categories whose source is **Local**.
- 3 Click **Delete**.

10.3.4 Creating a New Product Subcategory

Creating a subcategory further classifies a product.

- 1 In ZENworks Control Center, click **Configuration**, then click the **Asset Inventory** tab.
- 2 In the Product Categories panel, select a category that you want to create a subcategory for.
- 3 Click **Action > Manage Subcategories**.
The Product Subcategories panel appears, listing any predefined subcategories for the specified category, and the subcategory source, **Local** or **Novell**.
- 4 Click **New**.
- 5 Specify a name in the **Subcategory Name** field.
- 6 Click **OK**.

10.3.5 Renaming a Product Subcategory

- 1 In ZENworks Control Center, click **Configuration**, then click the **Asset Inventory** tab.
- 2 In the Product Categories panel, select the category whose subcategory you want to rename.
You can only rename subcategories whose source is **Local**.
- 3 Click **Action > Manage Subcategories**.
- 4 Select the category/subcategory pair.
- 5 Click **Edit > Rename**.

- 6 Specify a new name in the **Subcategory Name** field.
- 7 Click **OK**.

10.3.6 Deleting a Product Subcategory

- 1 In ZENworks Control Center, click **Configuration**, then click the **Asset Inventory** tab.
- 2 In the Product Categories panel, select the category whose subcategory you want to delete.
You can only delete subcategories whose source is **Local**.
- 3 Click **Action > Manage Subcategories**.
- 4 Select the category/subcategory pair you want to delete.
- 5 Click **Delete**.

11 Purge Inventory History

The obsolete inventory records can be deleted from the database. This process of deleting the inventory data is called purging the inventory history. In ZENworks Control Center, you can use the Purge Inventory History option available under inventory settings to purge the inventory records after a specific period of time.

In this section you will find information on the following:

- ♦ [Section 11.1, “Configuring Inventory History Purge Settings for the Zone,” on page 81](#)
- ♦ [Section 11.2, “Overriding Inventory History Purge Settings at the Device Level,” on page 82](#)

11.1 Configuring Inventory History Purge Settings for the Zone

The Purge Inventory History panel allows you to configure settings to delete the inventory history and the usage data. You can remove records from the database for the products and components that were previously marked for deletion and you can also delete software application usage data, network software usage data, and Web application usage data that is older than the value you set. By default, all the data is stored in the database unless this setting is configured. Purge schedule of the Zone is applicable to the devices as well.

- 1 In ZENworks Control Center, click the **Configuration** tab.
- 2 Click **Inventory** under **Management Zone Settings**.
- 3 Click **Purge Inventory History**.
- 4 Specify the following purge history settings:
 - ♦ **Remove the deleted products and components older than x day(s):** Specify the number of days after which to purge the deleted product and component data. The default value is 180 days.
 - ♦ **Remove the inventory history data older than x day(s):** Specify the number of days after which to purge the inventory history. The default value is 180 days.
 - ♦ **Remove the Software Application Usage data older than x day(s):** Specify the number of days after which to purge the software application usage data. The default value is 180 days.
 - ♦ **Remove the Network Software Usage data older than x day(s):** Specify the number of days after which to purge the network software usage data. The default value is 180 days.
 - ♦ **Remove the Web Application Usage data older than x day(s):** Specify the number of days after which to purge the Web application usage data. The default value is 180 days.

Example 11-1 For example:

If you enter 190 days as the value, all data older than 190 days is deleted.

- 5 Specify one of the following as the schedule for purging the history:
 - ♦ Select **Recurring** to set a schedule that enables the purging process to start at the specified time of the given day.
 - ♦ Select **Noschedule** if you do not want to purge the inventory data automatically.
- 6 Use the **Duration of the job in hours / run** option to specify the total duration in number of hours per run for the purging process
- 7 In the Dedicated Server to run Inventory Pruning field, browse for and select a Primary Server, then click OK. Pruning takes place on the chosen primary server. If you do not select any, then pruning takes place on any server.
- 8 Click **Apply** or **OK** to save your settings. Click **Reset** to return to the default values.

11.2 Overriding Inventory History Purge Settings at the Device Level

You can configure inventory history purge settings for the selected device or server. These settings allow you to remove the inventory history and application usage data as necessary.

The Purge Inventory History panel allows you to configure settings to remove the inventory history and the usage data. You can remove records from the database for the products and components that were previously marked for deletion and you can also delete software application usage data, network software usage data, and Web application usage data that is older than the value you set. By default, all the data is stored in the database unless this setting is configured. Device level purging is based on the Zone level purging schedule.

- 1 In ZENworks Control Center, click the **Devices** tab.
- 2 Click **Servers** or **Workstations**.

If you are configuring the purge inventory history settings on a device folder or a device, you need to click **Override Settings** before you can change the system settings.
- 3 Click a server name or a device name.
- 4 On the Settings page, click **Purge Inventory History**.
- 5 Specify the following purge history settings:
 - ♦ **Remove the deleted products and components older than x day(s):** Specify the number of days after which to purge the deleted product and component data. The default value is 180 days.
 - ♦ **Remove the inventory history data older than x day(s):** Specify the number of days after which to purge the inventory history. The default value is 180 days.
 - ♦ **Remove the Software Application Usage data older than x day(s):** Specify the number of days after which to purge the software application usage data. The default value is 180 days.
 - ♦ **Remove the Network Software Usage data older than x day(s):** Specify the number of days after which to purge the network software usage data. The default value is 180 days.
 - ♦ **Remove the Web Application Usage data older than x day(s):** Specify the number of days after which to purge the Web application usage data. The default value is 180 days.

Example 11-2 For example:

If you enter 190 days as the value, all data older than 190 days is deleted.

6 Click **Apply** or **OK** to save your settings. Click **Reset** to return to the default values.

A Inventory Workflow

- ♦ [Section A.1, “Inventory Workflow on a Workstation,” on page 85](#)
- ♦ [Section A.2, “Inventory Workflow on a Primary Server,” on page 85](#)
- ♦ [Section A.3, “Inventory Workflow on an Inventory Only Device,” on page 86](#)
- ♦ [Section A.4, “Troubleshooting the Inventory Workflow,” on page 86](#)

A.1 Inventory Workflow on a Workstation

For any scheduled inventory scan or user-initiated inventory scan, the collector performs the inventory scan and prepares the scanned file according to the collected data. The workstation then sends the file to the Collection Server which in turn forwards that file to the Primary Server for further processing. Only when Collection Servers are not available, the file is sent directly to the Primary Server for processing.

The collector places the following files:

`workstationguid-delta.xml`

`workstationguid-last.xml`

`workstationguid-full.xml`

in one of the following folders in the workstation:

On Linux devices: `/var/opt/novell/zenworks/work/inventory`

On Windows devices: `<Install -path>\ZENworks\work\inventory`

The `workstationguid-delta.xml` file displays only the current scan excluding the last scan. The `workstationguid-last.xml` file contains data related only to the current scan and the `workstationguid-full.xml` file includes complete details of all the scans so far.

The collector uploads only the delta file to the ZCM server while the other two files remain on the device and get updated during the next scan.

A.2 Inventory Workflow on a Primary Server

The Inventory Storer that is attached to the loader service wakes up every 30 seconds and checks one of the following folders:

For Windows Primary Server: `<Installed Path>ZENworks\work\collection\inventory`

For Linux Primary Server: `/var/opt/novell/zenworks/collection/inventory`

The Storer then picks up all the files in one of the above listed folders, which are saved as `<timestamp>-<device guid>-delta.zip` files. The Inventory Storer loads all the zipped files present in the folder, unzips the files, and sorts the files according to the time stamp per device. The unzipped files are stored in an XML format as `<timestamp>-<device guid>-delta.xml`.

The Inventory Storer then begins processing each file by creating a WIF object out of the extracted XML files. After the processing is complete, the data is moved to the database as part of processing of the WIF XML for that device. After the WIF processing is complete, the XML file is moved to either a success or failure folder under one of the following folders:

For Windows Primary Server: `<Installed Path>ZENworks\work\collection\inventory`

For Linux Primary Server: `/var/opt/novell/zenworks/collection/inventory`

The XML file is moved according to the errors caused by XML formats/database insert/update/delete issues that occurred during processing.

A.3 Inventory Workflow on an Inventory Only Device

For any scheduled inventory scan or user-initiated inventory scan, the Inventory-Only Agent device sends the file to only the Primary Server for processing. Collection Servers are not supported by Inventory-Only Agent devices.

A.4 Troubleshooting the Inventory Workflow

If you are unable to view the devices in ZENworks Control Center:

- 1 On the Primary Server, check the files in the `<Installed Path>ZENworks\work\collection\inventory` zipped folder to see if the loader is running.
- 2 If the loader is running, verify whether any PRU deploy or KBMerge process is also running as this stops the processing of WIF files until the process completes.
- 3 If none of these are running, check the `loader-messages.log` to see if you find any log message stating that the PRU version is not in synchronization with the LMPRU version. Apply the PRU as the LMPRU to ensure that the PRU versions are not in synchronization.

B Troubleshooting Asset Inventory

The following sections provide solutions to the problems you might encounter with ZENworks Asset Inventory:

- ♦ [“Unable To Install the Portable Collector on Windows Devices” on page 87](#)
- ♦ [“When you run an inventory scan on a Windows 10 device, an exception is logged in the log file” on page 88](#)
- ♦ [“Portable Inventory Collector might crash on some versions of Windows” on page 88](#)
- ♦ [“The ZENworks Agent on NetWare is unable to send inventory to the ZENworks Server or obtain settings from the ZENworks Server” on page 89](#)
- ♦ [“LDAP import tasks remain in a pending state if they run simultaneously” on page 89](#)
- ♦ [“An inventory-only managed device is unable to post scans” on page 90](#)
- ♦ [“Inventory data of a managed device is not displayed for the Linux Primary Server” on page 90](#)
- ♦ [“How do I enable debug logging?” on page 90](#)
- ♦ [“Unable to import the inventory data gathered with the Portable Collector in ZENworks Control Center” on page 90](#)
- ♦ [“Inventory data of a device reregistered from one Management Zone to another is not displayed” on page 91](#)
- ♦ [“Event-based and On Refresh schedules fail for the inventory scan and collection data form” on page 91](#)
- ♦ [“Inventory reports list duplicate components during an inventory scan in ZENworks Control Center” on page 91](#)
- ♦ [“Unable to inventory the BIOS details for Windows 7 64-bit devices that have SMBIOS 2.0 or earlier installed” on page 92](#)
- ♦ [“KB Merge failure might occur when Primary Servers are on different operating systems” on page 92](#)
- ♦ [“Optional fields are not visible in the LDAP Fields list in ZENworks Control Center” on page 93](#)
- ♦ [“On some Windows devices, the Usage Module Helper\(zcmumhelper.exe.\) crashes randomly” on page 94](#)
- ♦ [“From Windows 7 onwards, you might not be able to monitor the usage of Web applications on 64-bit devices” on page 94](#)
- ♦ [“Red Hat Enterprise Linux 8 Workstation class device is listed as a Server class device in ZENworks Control Center” on page 94](#)

Unable To Install the Portable Collector on Windows Devices

Source: The source of the message.

Explanation: When you download the Portable Collector using the Create Portable Client option and then you try to install it on Windows devices, the Portable Collector fails to install.

Action: After downloading and copying the Portable Collector on the target device perform the following steps:

1. Right-click the downloaded Portable Client (.zip) file.
2. In the General tab, in the Security section, click Unblock or select the Unblock checkbox.
3. Click Apply.

When you run an inventory scan on a Windows 10 device, an exception is logged in the log file

Source: ZENworks

Explanation: When you run the full inventory scan on a Windows 10 device, during the software collection, the following exception is logged in the ZMD messages log:

The specified path, file name, or both are too long. The fully qualified file name must be less than 260 characters, and the directory name must be less than 248 characters.

Action: In the Windows 10 Local Group Policy Editor, enable the Enable win32 long paths option.

To Enable win32 long paths on a managed device:

- 1 Click Start Menu and type gpedit.msc in the search field.
- 2 Open the Local Group Policy Editor window.
- 3 Go to **Computer Configuration > Administrative Templates > System > Filesystem**
- 4 On the right panel, open Enable win32 long paths.
- 5 In the **Enable win32 long paths** window, select **Enabled** and then click **OK**.
- 6 Restart the device.

To Enable win32 long paths on all managed devices in the zone:

In ZCC, create a Windows Group Policy to enable the win32longpaths and assign it to all the managed devices in the zone.

For more information, see [Windows Group Policy](#) section in the [ZENworks Configuration Policies Reference](#).

Portable Inventory Collector might crash on some versions of Windows

Source: ZENworks, ZENworks Portable Inventory Collector

Possible Cause: Due to Windows security restrictions, the ZENworks Portable Inventory Collector might crash.

Action: Before running ZENcollector.exe, ensure that you unblock the following files:

- ♦ ZenCollector.exe
- ♦ ZenCollectorHWCollectionFramework.dll
- ♦ ZenCollectorMainFramework.dll
- ♦ ZenCollectorSWCollectionFramework.dll
- ♦ ZenCollectorUtility.dll

NOTE: The files are available in the folder where you extract the portable.zip file.

To unblock the files:

1. Right-click the file, select **Properties**.
2. In the **Properties** window, click the **Unblock** button, and then click **OK**.

The ZENworks Agent on NetWare is unable to send inventory to the ZENworks Server or obtain settings from the ZENworks Server

Source: ZENworks; Asset Inventory.

Possible Cause 1: The IP address of the ZENworks server is incorrect.

Action 1: Configure the correct IP address:

- 1 In the `sys:\ZENworks\zaa\uiaconfig.xml` file, specify the correct IP address in the following line:

```
<server>ipaddress:80</server>
```

Replace *ipaddress* with the address of the server.

- 2 (Optional) To immediately post the scan, restart the zenaa module.

Possible Cause 2: The network connection or the ZENworks Server is down.

Action 2: Ensure that the ZENworks Server is up and running.

Possible Cause 3: The Primary Server has been configured to run on a port other than 80.

Action 3: Configure the correct port number:

- 1 In the `sys:\ZENworks\zaa\uiaconfig.xml` file, specify the correct port number in the following line:

```
<server>ipaddress:80</server>
```

where *ipaddress* is the address of the server.

- 2 (Optional) To immediately post the scan, restart the zenaa module.

LDAP import tasks remain in a pending state if they run simultaneously

Source: ZENworks; Asset Inventory.

Explanation: If an LDAP import task has not finished and you simultaneously run a new task, the new task is not started and remains in a pending state.

Possible Cause 1: Multiple tasks are running simultaneously.

Action 1: Before running a new task, ensure that all the existing tasks are in a finished state.

Possible Cause 2: Multiple tasks have been configured to run on the same schedule.

Action 2: Ensure that you do not set the same schedule for multiple tasks.

An inventory-only managed device is unable to post scans

Source: ZENworks; Asset Inventory.

Possible Cause: The `uiaconfig.xml` file might be corrupted.

Action: Do the following:

- 1 In the `uiaconfig.xml` file, add or change the IP address in the following line:

`Server="a.b.c.d"`

Replace *a.b.c.d* with the address of the server.

On Linux, `uiaconfig.xml` is located in `opt/novell/zenworks/umia`.

- 2 (Optional) To immediately post the scan, restart the `zenumia` service.

Inventory data of a managed device is not displayed for the Linux Primary Server

Source: ZENworks; Asset Inventory.

Explanation: The inventory data of managed devices is not displayed for the Linux Primary Server in ZENworks Control Center.

Action: Install the inventory-only agent on the Linux Primary Server. The Linux Primary Server is listed as an unmanaged device in ZCC (**Device > Inventoried**).

For information on how to install the `inventoronly` agent, see [ZENworks Discovery, Deployment, and Retirement Reference](#).

How do I enable debug logging?

Source: ZENworks; Asset Inventory.

Action: To enable the logs, see TID 3418069 in the [Micro Focus Support Knowledgebase](http://www.novell.com/support/search.do?usemicrosite=true&searchString=3418069) (<http://www.novell.com/support/search.do?usemicrosite=true&searchString=3418069>).

Unable to import the inventory data gathered with the Portable Collector in ZENworks Control Center

Source: ZENworks; Asset Inventory.

Possible Cause: In the inventory scan file, special characters such as &, #, or 1 are appended with the <DateInstalled> tag. For example:

```
<DateInstalled>&#1;</DateInstalled>
```

Action: Do the following:

- 1 In the .xml file from which you want to import the inventory data, remove all the special characters such as &, #, or 1 that were appended with the <DateInstalled> tag and ensure that the tag contains the following information only:

```
<DateInstalled></DateInstalled>
```

- 2 Import the inventory data again.

For more information on how to import the data, see [Section 3.6.4, "Importing Data Gathered with the Portable Collector,"](#) on page 30.

Inventory data of a device reregistered from one Management Zone to another is not displayed

Source: ZENworks; Asset Inventory.

Explanation: If a device is reregistered from one Management Zone to another, the inventory data is not displayed for the device in ZENworks Control Center.

Action: Initiate an inventory scan twice on the device.

For more information on how to initiate an inventory scan, see ["Scanning the Device"](#) in the ZENworks Agent.

Event-based and On Refresh schedules fail for the inventory scan and collection data form

Source: ZENworks; Asset Inventory.

Explanation: If an administrator configures an event-based or On Refresh schedule for an inventory scan and collection data form, the inventory agent fails to invoke the inventory scan and collection data form.

Action: Configure only a Recurring schedule for the inventory scan and collection data form.

Inventory reports list duplicate components during an inventory scan in ZENworks Control Center

Source: ZENworks; Asset Inventory.

Action: To troubleshoot the issue, see TID 7003350 in the [Micro Focus Support Knowledgebase](#) (<http://www.novell.com/support/search.do?usemicrosite=true&searchString=7003350>).

Unable to inventory the BIOS details for Windows 7 64-bit devices that have SMBIOS 2.0 or earlier installed

Source: ZENworks; Asset Inventory.

Explanation: If you want to inventory the BIOS details for Windows 7 64-bit devices, you must have SMBIOS 2.1 or later installed on these devices.

Action: None.

KB Merge failure might occur when Primary Servers are on different operating systems

Source: ZENworks; Asset Inventory.

Explanation: If there are multiple types of operating systems in an environment and if one Primary Server is on Windows and another Primary Server is on Linux, KB Merge might not finish in some cases. You see the following error message in ZENworks Control Center:

An error occurred during the KB Merge. If this problem persists, please contact Technical Support.

Action: If the first Primary Server is on Windows and the second Primary Server is on Linux, modify the path names for the second Primary Server:

- 1 On the Linux Primary Server, go to `/var/opt/novell/zenworks/tmp/kb/pre`.
- 2 The file names currently have the path as part of the file name. Rename the following files by removing the `C:\Program Files (x86)\Novell\ZENworks\conf\pru\` path:

Change file name from	Change file name to
C:\Program Files (x86)\Novell\ZENworks\conf\pru\ship.kb	ship.kb
C:\Program Files (x86)\Novell\ZENworks\conf\pru\pruver.tkb	pruver.tkb
C:\Program Files (x86)\Novell\ZENworks\conf\pru\iv.kb	iv.kb
C:\Program Files (x86)\Novell\ZENworks\conf\pru\LC_TallyProduct.txt	LC_TallyProduct.txt
C:\Program Files (x86)\Novell\ZENworks\conf\pru\LC_TallyProductMap.txt	LC_TallyProductMap.txt
C:\Program Files (x86)\Novell\ZENworks\conf\pru\LC_TallyProductSuite.txt	LC_TallyProductSuite.txt

Change file name from	Change file name to
C:\Program Files (x86)\Novell\ZENworks\conf\pru\LC_TallyProduct SuiteMap.txt	LC_TallyProductSuiteMap.txt

- 3 To trigger the KB Merge process in ZENworks Control Center, select **Configuration > Asset Inventory > Local Software Products**.
- 4 Select the products, click **Action**, then select **Update knowledgebase with Local Product Changes** to apply the changes.

Action: If the first Primary Server is on Linux and the second Primary Server is on Windows, modify the path names for the second Primary Server:

- 1 On the Windows Primary Server, go to
%ZENWORKS_HOME%\temp\kb\pre.
- 2 The file names currently have the path as part of the file name. Rename the following files by removing the /etc/opt/novell/zenworks/pru/ path:

Change file name from	Change file name to
/etc/opt/novell/zenworks/pru/ship.kb	ship.kb
/etc/opt/novell/zenworks/pru/pruver.tkb	pruver.tkb
/etc/opt/novell/zenworks/pru/iv.kb	iv.kb
/etc/opt/novell/zenworks/pru/ LC_TallyProduct.txt	LC_TallyProduct.txt
/etc/opt/novell/zenworks/pru/ LC_TallyProductMap.txt	LC_TallyProductMap.txt
/etc/opt/novell/zenworks/pru/ LC_TallyProductSuite.txt	LC_TallyProductSuite.txt
/etc/opt/novell/zenworks/pru/ LC_TallyProductSuiteMap.txt	LC_TallyProductSuiteMap.txt

- 3 To trigger the KB Merge process in ZENworks Control Center, select **Configuration > Asset Inventory > Local Software Products**.
- 4 Select the products, click **Action**, then select **Update knowledgebase with Local Product Changes** to apply the changes.

Optional fields are not visible in the LDAP Fields list in ZENworks Control Center

Source: ZENworks; Asset Inventory.

Explanation: Optional fields defined in the LDAP directory are not visible in the **LDAP Fields** list in the LDAP Import Task Mappings panel of ZENworks Control Center.

Possible Cause: The optional fields defined in the LDAP directory are not present in the `dirimport.xml` file, which is on the ZENworks Server.

Action: Update the `dirimport.xml` file with the optional fields. For example, if the optional field is **costCenter**, perform the following steps:

1 Locate the `dirimport.xml` file:

On Linux: `/etc/opt/novell/zenworks/loader/dirimport.xml`

On Windows: `ZENworks_HOME>\conf\loader\dirimport.xml`

2 Update the optional field in the following lines in the `dirimport.xml` file:

```
<Module>
<Class>com.novell.zenworks.loader.modules.Inventory
Import Module</Class>
<Parameters>
  <Parameter Name="sleep-interval">30000</Parameter>
  <Parameter Name="include-field">costCenter</
Parameter>
</Parameters>
</Module>
```

On some Windows devices, the Usage Module Helper(zcmumhelper.exe.) crashes randomly

Source: ZENworks; Asset Inventory

Explanation: On some Windows devices, `ZCMUMHelper.exe` which collects the web usage, network usage and other details of the logged in users might crash with a pop-up message.

Action: Rebooting the device might fix the problem.

From Windows 7 onwards, you might not be able to monitor the usage of Web applications on 64-bit devices

Source: ZENworks; Asset Inventory

Explanation: On 64-bit devices from Windows 7 onwards, you might not be able to collect or monitor the usage of the Web-based applications or pages.

Action: There is no workaround.

Red Hat Enterprise Linux 8 Workstation class device is listed as a Server class device in ZENworks Control Center

Source: ZENworks; Asset Inventory

Explanation: After installing the Inventory Only Agent (IOA) on an RHEL 8 workstation and registering the device to ZENworks by running the `zac ioa cfg <serverip>` command, when you log into ZCC, the device is wrongly listed in the Servers folder, instead of the Workstations folder of Inventoried Devices.

Possible Cause: The `syspurpose.json` file includes information related to whether the RHEL device is of Server class or Workstation class. However, when the subscription manager role is not enabled on the RHEL device, this information is not populated in the `syspurpose.json` file. Hence, the workstation is listed in the Servers folder instead of the Workstations folder of Inventoried Devices in ZCC.

Action: Enable the Subscription Manager role on the RHEL device and run the `zac ioa cfg <serverip>` command again.

